



Falcon Sensor for Linux Deployment Guide

CROWDSTRIKE CONFIDENTIAL

Last updated: Aug 6th, 2020

Contents:

- [Introduction](#)
- [System Requirements](#)
 - [Operating Systems](#)
 - [Networking Requirements](#)
 - [Allow TLS traffic](#)
- [Install the Falcon Sensor for Linux](#)
 - [Optional: Managing Sensor Tags](#)
 - [Optional: Installing to a CID that requires installation tokens](#)
 - [Optional: Prepare a host as a master image](#)
 - [Optional: Install with Pay-As-You-Go billing](#)
 - [Optional: Configure a proxy](#)
 - [Optional: Install with Package Signature Verification](#)
 - [Optional: Install on Ubuntu with Secure Boot Enabled](#)
- [Uninstall the Falcon Sensor for Linux](#)
- [Troubleshooting Sensor Installation](#)
 - [Installation Fails](#)
 - [Ubuntu Installation Fails: "Dependent Packages are not Installed"](#)
 - [SLES Installation Fails: "Nothing Provides Openssl"](#)
 - [Verify that Dependencies are Installed](#)
- [Troubleshooting General Sensor Issues](#)
 - [Verify that the Sensor is Running](#)
 - [Verify the Sensor Files on Disk](#)
 - [Verify that the Sensor is Connected to the Cloud](#)
- [Sensor Logging](#)
- [Appendix A: Supported kernels](#)
 - [Amazon Linux 1](#)
 - [Amazon Linux 2](#)
 - [Amazon Linux 2018.03](#)
 - [Amazon Linux 2018.04](#)
 - [Amazon Linux 2017.03](#)
 - [Amazon Linux 2017.09](#)
 - [Debian 9](#)
 - [Oracle Linux 6](#)
 - [Oracle Linux 7](#)
 - [RHEL 6 / CentOS 6](#)
 - [RHEL 7 / CentOS 7](#)
 - [RHEL 8 / CentOS 8](#)
 - [RHEL/CentOS 8.1](#)
 - [RHEL/CentOS 8.2](#)
 - [SLES 11 SP1](#)
 - [SLES 11 SP4](#)
 - [SLES 12 SP1](#)
 - [SLES 12 SP2](#)
 - [SLES 12 SP3](#)
 - [SLES 12 SP4](#)
 - [SLES 12 SP5](#)
 - [SLES 15](#)

- [SLES 15 SP1](#)
- [Ubuntu 14.04LTS](#)
- [Ubuntu 16.04LTS](#)
- [Ubuntu 16.04.5](#)
- [Ubuntu 18.04 LTS](#)
- [Appendix B: Reduced functionality mode \(RFM\)](#)
 - [What happens to sensors in RFM?](#)
 - [How can I tell if my sensor's in RFM?](#)
 - [Returning an RFM sensor to full functionality](#)
 - [Need additional support?](#)
- [Appendix C: Falcon-Kernel-Check tool](#)
 - [Before You Begin](#)
 - [Extracting the tool](#)
 - [Checking Kernel Compatibility](#)
 - [Command Line Options](#)

Introduction

CROWDSTRIKE CONFIDENTIAL

This guide explains how to install, uninstall, and troubleshoot the Falcon sensor for Linux.

System Requirements

CROWDSTRIKE CONFIDENTIAL

Operating Systems

We support x86_64 and Graviton 64 versions of these Linux server OSes. For specific kernel versions, see [Appendix A](#).

X86_64

- Amazon Linux 2
- Amazon Linux AMI
 - 2018.03
 - 2017.09
 - 2017.03
- CentOS
 - 7.1 – 7.8
 - 6.7 – 6.10
 - 8.0 - 8.2
- Debian 9
- Oracle Linux
 - Oracle Linux 6 - UEK 3, 4
 - Oracle Linux 7 - UEK 3, 4, 5
 - Red Hat Compatible Kernel (supported RHCK kernels are the same as RHEL)
- Red Hat Enterprise Linux (RHEL)
 - 7.1-7.8
 - 6.7-6.10
 - 8.0 - 8.2
- SUSE Linux Enterprise
 - 15
 - 12.1 – 12.4
 - 11.4 (you must also install OpenSSL version 1.0.1e or greater)
- Ubuntu
 - 18-AWS
 - 18.04 LTS
 - 16-AWS
 - 16.04 LTS
 - 14.04 LTS

We support Linux servers and desktops running [supported long term support \(LTS\) kernels](#). Other kernel versions, such as custom or hardware enablement (HWE) are unsupported.

GRAVITON

We support Graviton versions of these Linux server OSes. For specific kernel versions, see [Appendix A](#).

- Amazon Linux 2

We support Linux servers and desktops running [supported long term support \(LTS\) kernels](#). Other kernel versions, such as custom or hardware enablement (HWE) are unsupported.

Cloud Machine Learning (ML) is unsupported on Graviton hosts at this time.

DOCKER SUPPORT

Please note that docker is supported on the following Linux OSes only:

- Amazon Linux 2 - LNX 5.26.9003+ required
- Amazon Linux 2018.03
- CentOS7 and RHEL 7 (CentOS 7.8/RHEL 7.8 require LNX sensor 5.30.9510+)
- Ubuntu 14.04, 16.04, and 18.04 (Ubuntu 18.04 requires LNX sensor 5.27.9101+)
- SLES 12 SP3
- SLES 12 SP4 and SLES 15 - LNX 5.26.9003+ required
- SLES 12 SP5 – LNX 5.28.9205+ required

Networking Requirements

Allow TLS traffic

Depending on your network environment, you may need to allow ("whitelist") TLS traffic between your network and our cloud's network addresses:

US-1 (most customers):

- ts01-b.cloudsink.net
- lfodown01-b.cloudsink.net

US-GOV-1:

- ts01-laggar-gcw.cloudsink.net
- lfodown01-laggar-gcw.cloudsink.net

EU-1:

- ts01-lanner-lion.cloudsink.net
- lfodown01-lanner-lion.cloudsink.net

US-2:

- ts01-gyr-maverick.cloudsink.net

- Ifodown01-gyr-maverick.cloudsink.net

If your network requires allowing by IP address instead of FQDN, see [Cloud IP Addresses](#) for a list of IP addresses we use.

We use AWS for some communications between hosts and the CrowdStrike cloud.

AVOID INTERFERENCE WITH CERTIFICATE PINNING

The Falcon sensor uses certificate pinning to defend against man-in-the-middle attacks. Some network configurations, such as deep packet inspection, interfere with certificate validation.

Disable deep packet inspection (also called "HTTPS interception," "TLS interception," or "SSL inspection") or similar network configurations. Common sources of interference with certificate pinning include antivirus systems, firewalls, or proxies.

Install the Falcon Sensor for Linux

CROWDSTRIKE CONFIDENTIAL

1. Download the Falcon sensor installer from [Hosts > Sensor Downloads](#).
2. Copy your Customer ID Checksum (CID), displayed on Sensor Downloads.
3. Run the installer, substituting `<installer_filename>` with your installer's file name.
 - Ubuntu: `sudo dpkg -i <installer_filename>`
 - RHEL, CentOS, Amazon Linux: `sudo yum install <installer_filename>`
 - SLES: `sudo zypper install <installer_filename>`
4. Set your CID on the sensor, substituting `<CID>` with your CID. This step is not required for versions 4.0 and earlier.
 - All OSes: `sudo /opt/CrowdStrike/falconctl -s --cid=<CID>`
5. Start the sensor manually. This step is not required for versions 4.0 and earlier.
 - Hosts with SysVinit: `service falcon-sensor start`
 - Hosts with Systemd: `systemctl start falcon-sensor`
6. Confirm the sensor is running.
 - All OSes: `ps -e | grep falcon-sensor`

You'll see output similar to this:

```
[root@centos6-installtest ~]# sudo ps -e | grep falcon-sensor
905 ?          00:00:02 falcon-sensor
```

Optional: Managing Sensor Tags

Sensor tags are optional user-defined identifiers you can use to group and filter hosts.

ASSIGNING SENSOR TAGS

Assign tags to a host using the `--tags` switch. This switch is case sensitive.

Tags can include these characters:

- letters (a-z,A-Z)
- numbers (0-9)
- hyphens (-)
- underscores (_)
- forward slashes (/)

Tags can't include spaces () or commas (,).

To assign multiple tags, separate each tag with commas. All tags for a host, including comma separators, cannot exceed 256 characters.

For example, to add the tags `Washington/DC_USA` and `Production` to a host, use this syntax:

```
sudo /opt/CrowdStrike/falconctl -s --tags="Washington/DC_USA,Production"
```

To see the tags currently assigned to a host, use the `-g` option:

```
sudo /opt/CrowdStrike/falconctl -g --tags
```

Tags take effect the next time the sensor is restarted.

To restart a sensor with SystemD: `systemctl restart falcon-sensor`

To restart a sensor with SysVinit: `service falcon-sensor start`

REMOVING SENSOR TAGS

To remove all tags from a host:

```
sudo /opt/CrowdStrike/falconctl -d -f --tags
```

Tags take effect the next time the sensor is restarted.

To restart a sensor with SystemD: `systemctl restart falcon-sensor`

To restart a sensor with SysVinit: `service falcon-sensor start`

Optional: Installing to a CID that requires installation tokens

[Installation tokens](#) prevent unauthorized hosts from being accidentally or maliciously added to your customer ID (CID).

Installation tokens are an optional security measure for your CID. To use installation tokens, you create one or more tokens in the Falcon console or via the API, enable the token requirement, and then provide the tokens to sensors at installation time.

When you install a sensor after enabling **Require tokens**, the `falconctl` command must include an additional parameter and an active token:

```
sudo /opt/CrowdStrike/falconctl -s --cid=<CID> --provisioning-token=ABCD1234
```

Optional: Prepare a host as a master image

If you're preparing a host as a "master" device for cloning or virtualization, you must remove your "master" host's agent ID (AID).

To create a new master image template with no agent ID and Pay-As-You-Go billing enabled:

1. Prepare your master image instance, including any software configuration or updates.
2. Download the Falcon sensor installer from [Hosts > Sensor Downloads](#) or via [sensor download APIs](#).
3. Copy your Customer ID Checksum (CID), displayed on Sensor Downloads.
4. Run the installer, substituting `<installer_filename>` with your installer's file name.

- Ubuntu: `sudo dpkg -i <installer_filename>`

- RHEL, CentOS, Amazon Linux: `sudo yum install <installer_filename>`

- SLES: `sudo zypper install <installer_filename>`

5. After installing, run these `falconctl` commands to remove the host's agent ID, set your customer ID (CID), and configure the sensor for Pay-As-You-Go billing:

```
sudo /opt/CrowdStrike/falconctl -d -f --aid
sudo /opt/CrowdStrike/falconctl -s --cid=<CID>
sudo /opt/CrowdStrike/falconctl -s --billing=metered
```


6. Configure your cloud workloads to create ephemeral images based on this master image.
7. According to your organization's update policies, plan to regularly re-create this master image using an up-to-date Falcon sensor installer.

To automate this more effectively, consider using [sensor download APIs](#) to automatically retrieve new versions of the Falcon sensor. Then, use your organization's existing automation tools to install the newer version on your master image without an agent ID.

To change an existing Falcon sensor to use Pay-As-You-Go billing, run this `falconctl` command, then restart the sensor:

```
sudo /opt/CrowdStrike/falconctl -s --billing=metered
```

When your cloned devices or virtual machines first contact the CrowdStrike cloud, they'll be automatically assigned a unique AID. If multiple devices use the same AID, the Falcon console will process all their events as though they came from a single device.

Optional: Install with Pay-As-You-Go billing

See [Falcon for Cloud Workloads](#) for more info.

To create a new master image template with no agent ID and Pay-As-You-Go billing enabled:

1. Prepare your master image instance, including any software configuration or updates.
2. Download the Falcon sensor installer from [Hosts > Sensor Downloads](#) or via [sensor download APIs](#).
3. Copy your Customer ID Checksum (CID), displayed on Sensor Downloads.
4. Run the installer, substituting `<installer_filename>` with your installer's file name.
 - Ubuntu: `sudo dpkg -i <installer_filename>`
 - RHEL, CentOS, Amazon Linux: `sudo yum install <installer_filename>`
 - SLES: `sudo zypper install <installer_filename>`
5. After installing, run these `falconctl` commands to remove the host's agent ID, set your customer ID (CID), and configure the sensor for Pay-As-You-Go billing:

```
sudo /opt/CrowdStrike/falconctl -d -f --aid
sudo /opt/CrowdStrike/falconctl -s --cid=<CID>
sudo /opt/CrowdStrike/falconctl -s --billing=metered
```

6. Configure your cloud workloads to create ephemeral images based on this master image.
7. According to your organization's update policies, plan to regularly re-create this master image using an up-to-date Falcon sensor installer.

To automate this more effectively, consider using [sensor download APIs](#) to automatically retrieve new versions of the Falcon sensor. Then, use your organization's existing automation tools to install the newer version on your master image without an agent ID.

To change an existing Falcon sensor to use Pay-As-You-Go billing, run this `falconctl` command, then restart the sensor:

```
sudo /opt/CrowdStrike/falconctl -s --billing=metered
```

Optional: Configure a proxy

If your hosts use a proxy, configure the Falcon sensor to use it:

- **Configure proxy:** `sudo /opt/CrowdStrike/falconctl -s --aph=<proxy host> --app=<proxy port>`
- **Confirm config:** `sudo /opt/CrowdStrike/falconctl -g --aph --app`
- **Enable proxy:** `sudo /opt/CrowdStrike/falconctl -s --apd=FALSE`
- **Disable proxy:** `sudo /opt/CrowdStrike/falconctl -s --apd=TRUE`

Optional: Install with Package Signature Verification

For hosts with signature verification enabled, it needs to validate the sensor package's signature. To do this, download and import the RPM signing, GPG key from [Tools Download](#). That verifies the key during installation.

If the key hasn't been imported, hosts requiring the signature key generate an error similar to this one during the install. When this error occurs, try downloading and importing the key again.

```
falcon-sensor-4.5.0-5011.suse12.x86_64 (Plain RPM files cache): Signature verification failed [4-Signatures public key is not available]
```

To import the key :

1. Download `falcon-sensor.gpg` from [Tools Download](#)
2. Place it in your working directory
3. Run the import command from your working directory with elevated permissions:

```
# rpm --import falcon-sensor.gpg
```

4. Run the [sensor installation](#)

For more information on signature verification, refer to your distro's documentation, such as the Red Hat [Deployment Guide](#).

Optional: Install on Ubuntu with Secure Boot Enabled

Ubuntu hosts running with Secure Boot enabled require a CrowdStrike public key to load signed kernel modules. This allows signed kernel modules to load, preventing the sensor going into [Reduced Functionality Mode \(RFM\)](#).

Host running with Secure Boot enabled will see a similar message in `dmesg`:

```
[ 0.000000] secureboot: Secure boot enabled
[ 0.000000] Kernel is locked down from EFI secure boot; see man kernel_lockdown.7
```

This process requires:

- Ubuntu 18.04
- OpenSSL (`apt-get install openssl`)
- Mokutil (`apt-get install mokutil`)
- `crowdstrike_signing.x509` public signing key (obtain from [CrowdStrike Support](#))

1. REQUEST THE CROWDSTRIKE PUBLIC SIGNING KEY FOR UBUNTU FROM SUPPORT

2. IMPORT CROWDSTRIKE'S PUBLIC SIGNING KEY

1. Using `mokutil`, import `crowdstrike_signing.x509` public key to `MOK.der`:

```
mokutil --import <yourpath>/crowdstrike_signing.x509
```

Where `<yourpath>` is where you've saved the certificate.

2. Create a `mokutil` password. It's needed to enroll the key later, and is separate from your root/system password.

3. REBOOT YOUR HOST

4. ENROLL MACHINE-OWNER KEY (MOK)

Before the GRUB menu you are prompted to Enroll MOK. Follow the on-screen menus to enroll your keys. You can also use the View Key option to verify keys. Enter your password from the `mokutil --import` process.

5. VERIFY KEYS ARE ADDED TO KERNEL

1. Run this command: `sudo cat /proc/keys | grep crowdstrike`

2. When keys are added the output should be similar to:

```
asymmetri CrowdStrike, Inc: www.crowdstrike.com: <hash>: X509.rsa
```

6. VERIFY HOST IS NO LONGER IN RFM

Upon reboot, verify all kernel modules are loaded and the sensor is no longer in RFM:

```
lsmod | grep falcon
```

```
sudo /opt/CrowdStrike/falconctl -g --rfm-state
```

Signing of keys results in output: `rfm-state=false`

If output contains `rfm-state=true`, the sensor is still in RFM.

For additional troubleshooting information, visit the [Support Portal](#) or [submit a case](#) to CrowdStrike Support.

Uninstall the Falcon Sensor for Linux

CROWDSTRIKE CONFIDENTIAL

Run these commands to uninstall the Falcon sensor from your host:

- **Ubuntu:** `sudo apt-get purge falcon-sensor`
- **RHEL, CentOS, Amazon Linux:** `sudo yum remove falcon-sensor`
- **SLES:** `sudo zypper remove falcon-sensor`

Troubleshooting Sensor Installation

CROWDSTRIKE CONFIDENTIAL

Installation Fails

ISSUE

Your sensor installation fails.

SOLUTION

Verify that the SHA-256 checksum of the installer file you downloaded matches the SHA-256 checksum shown in [Hosts > Downloads](#).

Ubuntu Installation Fails: "Dependent Packages are not Installed"

ISSUE

Your Ubuntu installation fails with an error that "dependent packages are not installed."

SOLUTION

Use this command to install the dependent packages:

```
$ apt-get -f install
```

SLES Installation Fails: "Nothing Provides Openssl"

ISSUE

Your SLES installation fails with an error that `nothing provides openssl1 >= 1.0.1`. This is most commonly caused by a SLES version that doesn't include a modern OpenSSL implementation.

SOLUTION

1. Enable the SLES 11 security module: `$ sudo zypper mr --enable SLE11-Security-Module`
2. Run the sensor installer again.

Verify that Dependencies are Installed

ISSUE

Your installation fails with an error message about missing dependencies of libssl, libc, or libcrypto.

```
--> Missing Dependency: libssl.so.10()(64bit) is needed by package falcon-sensor-1.0.3-1.e16x86_64 (/falcon-sensor-1.0.3-1.e16.x86_64)
Error Missing Dependency: libc.so.6(GLIBC_2.7)(64bit) is needed by package falcon-sensor-1.0.3-1.e16x86_64 (/falcon-sensor-1.0.3-1.e16.x86_64)
Error Missing Dependency: libcrypto.so.10()(64bit) is needed by package falcon-sensor-1.0.3-1.e16x86_64 (/falcon-sensor-1.0.3-1.e16.x86_64)
```

SOLUTION

Install a [supported version](#) of OpenSSL.

Troubleshooting General Sensor Issues

CROWDSTRIKE CONFIDENTIAL

Verify that the Sensor is Running

1. Check running processes to verify the Falcon sensor is running: `ps -e | grep -e falcon-sensor`
2. Check kernel modules to verify the Falcon sensor's kernel modules are running: `lsmod | grep falcon`
3. Check the Falcon sensor's configurable options: `sudo /opt/CrowdStrike/falconctl -g`

Optional parameters:

- `--aid`: the sensor's agent ID
- `--cid`: your Customer ID
- `--apd`: the sensor's proxy status (enabled or disabled)
- `--aph`: the sensor's proxy host
- `--app`: the sensor's proxy port


The sensor requires these runtime services:

- network
- systemd
 - local-fs
 - sysinit
 - multi-user
 - shutdown

Verify the Sensor Files on Disk

If the sensor is not running, verify that the sensor's application files exist on your host:

```
$ sudo ls -al /opt/CrowdStrike /opt/CrowdStrike/falcon-sensor
```



This should be a symlink to either:

- the original sensor installation at `/opt/CrowdStrike/falcon-sensor`
- a sensor update package with a release build number, such as `/opt/CrowdStrike/falcon-sensor3000`


Verify that the Sensor is Connected to the Cloud

There are two ways to verify that a sensor is connected to the CrowdStrike cloud:

- **Falcon console:** Search for the host in [Hosts > Host Management](#). To view a complete list of newly installed sensors, use the [Sensor Report](#).
- **From the host:** Check network statistics using the command line: `sudo netstat -tapn | grep falcon`

If the Falcon sensor is communicating with the cloud, you'll see output like this:

```
tcp      0      0  192.0.2.176:35382    ec2-54-148-96-12:443  
ESTABLISHED 3228/falcon-sensor
```



Sensor Logging

CROWDSTRIKE CONFIDENTIAL

Providing logs to our support team can help diagnose sensor issues. Logs are stored within your host's syslog.

Syslog locations vary, but are specified in `/etc/syslog.conf` or `rsyslog.conf`, with these being the most common:

- `/var/log/messages`
- `var/log/syslog`
- `/var/log/rsyslog`
- `/var/log/daemon`

grep for the string `falcon` for sensor logs:

example: `sudo grep falcon /var/log/messages | tail -n 100`

Logs are kept according to your host's log rotation settings. For assistance gathering or reviewing logs, contact [Support](#).

Appendix A: Supported kernels

CROWDSTRIKE CONFIDENTIAL

Run the command `uname -r` from a host's command line to find its kernel version.

Unsupported kernels: For kernels not listed here, the sensor will run in a reduced functionality mode (RFM) until we update the Falcon sensor to support that kernel.

Amazon Linux 1

Kernel	Minimum sensor version
4.14.181-108.257.amzn1.x86_64	Falcon sensor v5.32.9705
4.14.186-110.268.amzn1.x86_64	Falcon sensor 5.34.9917

Amazon Linux 2

Kernel	Minimum sensor version
4.14.47-64.38.amzn2.x86_64	Falcon sensor v4.12.5704
4.14.51-66.38.amzn2.x86_64	Falcon sensor v4.12.5704
4.14.55-68.37.amzn2.x86_64	Falcon sensor v4.12.5704
4.14.59-68.43.amzn2.x86_64	Falcon sensor v4.13.5803
4.14.62-70.117.amzn2.x86_64	Falcon sensor v4.13.5803
4.14.67-71.56.amzn2.x86_64	Falcon sensor v4.13.5806
4.14.70-72.55.amzn2.x86_64	Falcon sensor v4.13.5806
4.14.72-73.55.amzn2.x86_64	Falcon sensor v4.16.6101
4.14.77-80.57.amzn2.x86_64	Falcon sensor v4.16.6109
4.14.77-81.59.amzn2.x86_64	Falcon sensor v4.16.6109
4.14.77-86.82.amzn2.x86_64	Falcon sensor v4.18.6402
4.14.88-88.73.amzn2.x86_64	Falcon sensor v4.18.6403
4.14.88-88.76.amzn2.x86_64	Falcon sensor v4.18.6404
4.14.94-89.73.amzn2.x86_64	Falcon sensor v4.21.6703
4.14.97-90.72.amzn2.x86_64	Falcon sensor v4.22.6805
4.14.101-91.76.amzn2.x86_64	Falcon sensor v4.23.6903
4.14.104-95.84.amzn2.x86_64	Falcon sensor v4.24.7002
4.14.106-97.85.amzn2.x86_64	Falcon sensor v4.25.7103
4.14.109-99.92.amzn2.x86_64	Falcon sensor v4.28.7303
4.14.114-103.97.amzn2.x86_64	Falcon sensor v4.28.7304
4.14.114-105.126.amzn2.x86_64	Falcon sensor v5.10.7403
4.14.121-109.96.amzn2.x86_64	Falcon sensor v5.11.7503
4.14.123-111.109.amzn2.x86_64	Falcon sensor v5.12.7602
4.14.128-112.105.amzn2.x86_64	Falcon sensor v5.12.7603
4.14.133-113.105.amzn2.x86_64	Falcon sensor v5.15.7901

4.14.133-113.112.amzn2.x86_64	Falcon sensor v5.16.8002
4.14.138-114.102.amzn2.x86_64	Falcon sensor v5.17.8103
4.14.143-118.123.amzn2.x86_64	Falcon sensor v5.18.8202
4.14.146-119.123.amzn2.x86_64	Falcon sensor v5.18.8203
4.14.146-120.181.amzn2.x86_64	Falcon sensor v5.20.8404
4.14.152-124.171.amzn2.x86_64	Falcon sensor v5.20.8406
4.14.152-127.182.amzn2.x86_64	Falcon sensor v5.20.8406
4.14.154-128.181.amzn2	Falcon sensor v5.23.8701
4.14.158-129.185.amzn2.x86_64	Falcon sensor v5.25.8902
4.14.165-131.185.amzn2.x86_64	Falcon sensor v5.26.9003
4.14.165-133.209.amzn2.x86_64	Falcon sensor v5.27.9104
4.19.58-21.57.amzn2.x86_64	Falcon sensor v5.27.9104
4.19.58-21.64.amzn2.x86_64	Falcon sensor v5.27.9104
4.19.66-22.57.amzn2.x86_64	Falcon sensor v5.27.9104
4.19.72-25.58.amzn2.x86_64	Falcon sensor v5.27.9104
4.19.75-27.58.amzn2.x86_64	Falcon sensor v5.27.9104
4.19.75-28.73.amzn2.x86_64	Falcon sensor v5.27.9104
4.19.82-30.69.amzn2.x86_64	Falcon sensor v5.27.9104
4.19.84-33.70.amzn2.x86_64	Falcon sensor v5.27.9104
4.14.171-136.231.amzn2.x86_64	Falcon sensor v5.28.9205
4.14.177-139.253.amzn2.x86_64	Falcon sensor v5.31.9607
4.14.177-139.254.amzn2.x86_64	Falcon sensor v5.31.9607
4.14.181-140.257.amzn2.x86_64	Falcon sensor v5.33.9804
4.14.181-142.260.amzn2.x86_64	Falcon sensor v5.33.9808
4.14.186-146.268.amzn2.x86_64	Falcon sensor v5.34.9917
4.14.77-86.82.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.88-88.73.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.88-88.76.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.94-89.73.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.97-90.72.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.101-91.76.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.104-95.84.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.106-97.85.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.109-99.92.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.114-103.97.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.114-105.126.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.121-109.96.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.123-111.109.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.128-112.105.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.133-113.105.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.133-113.112.amzn2.aarch64	Falcon sensor v5.34.9917

4.14.138-114.102.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.143-118.123.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.146-119.123.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.146-120.181.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.152-124.171.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.152-127.182.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.154-128.181.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.173-137.228.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.173-137.229.amzn2.aarch64	Falcon sensor v5.34.9917
4.14.181-140.257.amzn2.aarch64	Falcon sensor v5.34.9917
4.19.58-21.57.amzn2.aarch64	Falcon sensor v5.34.9917
4.19.58-21.64.amzn2.aarch64	Falcon sensor v5.34.9917
4.19.66-22.57.amzn2.aarch64	Falcon sensor v5.34.9917
4.19.72-25.58.amzn2.aarch64	Falcon sensor v5.34.9917
4.19.75-27.58.amzn2.aarch64	Falcon sensor v5.34.9917
4.19.75-28.73.amzn2.aarch64	Falcon sensor v5.34.9917
4.19.82-30.69.amzn2.aarch64	Falcon sensor v5.34.9917
4.19.84-33.70.amzn2.aarch64	Falcon sensor v5.34.9917

Amazon Linux 2018.03

Kernel	Minimum sensor version
4.14.26-46.32.amzn1.x86_64	Falcon sensor v4.10.5501
4.14.33-51.34.amzn1.x86_64	Falcon sensor v4.10.5501
4.14.33-51.37.amzn1.x86_64	Falcon sensor v4.10.5501
4.14.42-52.37.amzn1.x86_64	Falcon sensor v4.10.5501
4.14.47-56.37.amzn1.x86_64	Falcon sensor v4.10.5501
4.14.51-60.37.amzn1.x86_64	Falcon sensor v4.11.5605
4.14.51-60.38.amzn1.x86_64	Falcon sensor v4.11.5605
4.14.59-64.43.amzn1.x86_64	Falcon sensor v4.11.5607
4.14.62-65.117.amzn1.x86_64	Falcon sensor v4.11.5609
4.14.67-66.56.amzn1.x86_64	Falcon sensor v4.13.5803
4.14.70-67.55.amzn1.x86_64	Falcon sensor v4.13.5806
4.14.72-68.55.amzn1.x86_64	Falcon sensor v4.13.5809
4.14.77-69.57.amzn1.x86_64	Falcon sensor v4.16.6109
4.14.77-70.59.amzn1.x86_64	Falcon sensor v4.16.6109
4.14.77-70.82.amzn1.x86_64	Falcon sensor v4.18.6402
4.14.88-72.73.amzn1.x86_64	Falcon sensor v4.18.6403
4.14.88-72.76.amzn1.x86_64	Falcon sensor v4.18.6404
4.14.94-73.73.amzn1.x86_64	Falcon sensor v4.21.6703
4.14.97-74.72.amzn1.x86_64	Falcon sensor v4.21.6705

4.14.101-75.76.amzn1.x86_64	Falcon sensor v4.24.7002
4.14.104-78.84.amzn1.x86_64	Falcon sensor v4.24.7002
4.14.106-79.86.amzn1.x86_64	Falcon sensor v4.25.7103
4.14.109-80.92.amzn1.x86_64	Falcon sensor v4.26.7203
4.14.114-82.97.amzn1.x86_64	Falcon sensor v4.28.7304
4.14.114-83.126.amzn1.x86_64	Falcon sensor v5.10.7403
4.14.121-85.96.amzn1.x86_64	Falcon sensor v5.11.7503
4.14.123-86.109.amzn1.x86_64	Falcon sensor v5.12.7602
4.14.128-87.105.amzn1.x86_64	Falcon sensor v5.12.7603
4.14.133-88.105.amzn1.x86_64	Falcon sensor v5.15.7901
4.14.133-88.112.amzn1.x86_64	Falcon sensor v5.16.8002
4.14.138-89.102.amzn1.x86_64	Falcon sensor v5.17.8103
4.14.143-91.122.amzn1.x86_64	Falcon sensor v5.18.8202
4.14.146-93.123.amzn1.x86_64	Falcon sensor v5.18.8203
4.14.152-98.182.amzn1.x86_64	Falcon sensor v5.20.8406
4.14.154-99.181.amzn1	Falcon sensor v5.23.8701
4.14.158-101.185.amzn1.x86_64	Falcon sensor v5.25.8902
4.14.165-102.185.amzn1.x86_64	Falcon sensor v5.26.9003
4.14.165-103.209.amzn1.x86_64	Falcon sensor v5.27.9104
4.14.171-105.231.amzn1.x86_64	Falcon sensor v5.29.9402
4.14.173-106.229.amzn1.x86_64	Falcon sensor v5.31.9606

Amazon Linux 2018.04

Kernel	Minimum sensor version
4.14.177-107.254.amzn1.x86_64	Falcon sensor v5.31.9607

Amazon Linux 2017.03

Kernel	Minimum sensor version
4.9.17-8.31.amzn1.x86_64	Falcon sensor v3.5
4.9.20-10.30.amzn1.x86_64	Falcon sensor v3.5
4.9.20-11.31.amzn1.x86_64	Falcon sensor v3.5
4.9.27-14.31.amzn1.x86_64	Falcon sensor v3.5
4.9.27-14.33.amzn1.x86_64	Falcon sensor v3.5
4.9.32-15.41.amzn1.x86_64	Falcon sensor v3.5
4.9.38-16.33.amzn1.x86_64	Falcon sensor v3.5
4.9.38-16.35.amzn1.x86_64	Falcon sensor v3.6
4.9.43-17.38.amzn1.x86_64	Falcon sensor v3.6
4.9.43-17.39.amzn1.x86_64	Falcon sensor v3.7
4.9.51-10.52.amzn1.x86_64	Falcon sensor v3.7

4.9.70-25.242.amzn1.x86_64	Falcon sensor v3.8
4.9.75-25.55.amzn1.x86_64	Falcon sensor v3.8

Amazon Linux 2017.09

Kernel	Minimum sensor version
4.9.58-18.51.amzn1.x86_64	Falcon sensor v3.10.4204
4.9.58-18.55.amzn1.x86_64	Falcon sensor v3.10.4204
4.9.62-21.56.amzn1.x86_64	Falcon sensor v3.10.4204
4.9.77-31.58.amzn1.x86_64	Falcon sensor v3.10.4205
4.9.81-35.56.amzn1.x86_64	Falcon sensor v4.1.4404
4.9.76-3.78.amzn1.x86_64	Falcon sensor v4.3.4603
4.9.85-37.55.amzn1.x86_64	Falcon sensor v4.3.4603
4.9.85-38.58.amzn1.x86_64	Falcon sensor v4.3.4603
4.9.93-41.60.amzn1.x86_64	Falcon sensor v4.5.5014
4.9.70-22.55.amzn1.x86_64	Falcon sensor v4.11.5605
4.9.116-43.59.amzn1.x86_64	Falcon sensor v4.11.5607
4.9.119-44.140.amzn1.x86_64	Falcon sensor v4.11.5609

Debian 9

Kernel	Minimum sensor version
4.9.0-1-amd64_4.9.2-2	Falcon sensor v5.33.9804
4.9.0-1-amd64_4.9.6-3	Falcon sensor v5.33.9804
4.9.0-2-amd64_4.9.10-1	Falcon sensor v5.33.9804
4.9.0-2-amd64_4.9.13-1	Falcon sensor v5.33.9804
4.9.0-2-amd64_4.9.18-1	Falcon sensor v5.33.9804
4.9.0-3-amd64_4.9.25-1	Falcon sensor v5.33.9804
4.9.0-3-amd64_4.9.30-2+deb9u3	Falcon sensor v5.33.9804
4.9.0-3-amd64_4.9.30-2+deb9u1	Falcon sensor v5.33.9804
4.9.0-3-amd64_4.9.30-2+deb9u5	Falcon sensor v5.33.9804
4.9.0-3-amd64_4.9.30-2+deb9u4	Falcon sensor v5.33.9804
4.9.0-3-amd64_4.9.30-2+deb9u2	Falcon sensor v5.33.9804
4.9.0-3-amd64_4.9.30-1	Falcon sensor v5.33.9804
4.9.0-3-amd64_4.9.30-2	Falcon sensor v5.33.9804
4.9.0-4-amd64_4.9.47-1	Falcon sensor v5.33.9804
4.9.0-4-amd64_4.9.51-1	Falcon sensor v5.33.9804
4.9.0-4-amd64_4.9.65-3+deb9u1	Falcon sensor v5.33.9804
4.9.0-4-amd64_4.9.65-1	Falcon sensor v5.33.9804
4.9.0-4-amd64_4.9.65-3	Falcon sensor v5.33.9804
4.9.0-5-amd64_4.9.65-3+deb9u2	Falcon sensor v5.33.9804

4.9.0-5-amd64_4.9.80-1	Falcon sensor v5.33.9804
4.9.0-5-amd64_4.9.80-2	Falcon sensor v5.33.9804
4.9.0-6-amd64_4.9.82-1+deb9u2	Falcon sensor v5.33.9804
4.9.0-6-amd64_4.9.82-1+deb9u3	Falcon sensor v5.33.9804
4.9.0-6-amd64_4.9.88-1+deb9u1	Falcon sensor v5.33.9804
4.9.0-6-amd64_4.9.88-1	Falcon sensor v5.33.9804
4.9.0-7-amd64_4.9.107-1	Falcon sensor v5.33.9804
4.9.0-7-amd64_4.9.110-3+deb9u1	Falcon sensor v5.33.9804
4.9.0-7-amd64_4.9.110-3+deb9u2	Falcon sensor v5.33.9804
4.9.0-7-amd64_4.9.110-1	Falcon sensor v5.33.9804
4.9.0-7-amd64_4.9.110-2	Falcon sensor v5.33.9804
4.9.0-7-amd64_4.9.110-3	Falcon sensor v5.33.9804
4.9.0-8-amd64_4.9.110-3+deb9u4	Falcon sensor v5.33.9804
4.9.0-8-amd64_4.9.110-3+deb9u5	Falcon sensor v5.33.9804
4.9.0-8-amd64_4.9.110-3+deb9u3	Falcon sensor v5.33.9804
4.9.0-8-amd64_4.9.110-3+deb9u6	Falcon sensor v5.33.9804
4.9.0-8-amd64_4.9.130-1	Falcon sensor v5.33.9804
4.9.0-8-amd64_4.9.130-2	Falcon sensor v5.33.9804
4.9.0-9-amd64_4.9.161-1	Falcon sensor v5.33.9804
4.9.0-9-amd64_4.9.168-1+deb9u2	Falcon sensor v5.33.9804
4.9.0-9-amd64_4.9.168-1+deb9u3	Falcon sensor v5.33.9804
4.9.0-9-amd64_4.9.168-1+deb9u4	Falcon sensor v5.33.9804
4.9.0-9-amd64_4.9.168-1+deb9u5	Falcon sensor v5.33.9804
4.9.0-9-amd64_4.9.168-1	Falcon sensor v5.33.9804
4.9.0-10-amd64_4.9.184-1	Falcon sensor v5.33.9804
4.9.0-10-amd64_4.9.185-1	Falcon sensor v5.33.9804
4.9.0-11-amd64_4.9.189-3+deb9u2	Falcon sensor v5.33.9804
4.9.0-11-amd64_4.9.189-3+deb9u1	Falcon sensor v5.33.9804
4.9.0-11-amd64_4.9.189-1	Falcon sensor v5.33.9804
4.9.0-11-amd64_4.9.189-2	Falcon sensor v5.33.9804
4.9.0-11-amd64_4.9.189-3	Falcon sensor v5.33.9804
4.9.0-12-amd64_4.9.210-1	Falcon sensor v5.33.9804
4.9.0-12-amd64	Falcon sensor v5.33.9808
4.9.0-13-amd64	Falcon sensor v5.34.9917

Oracle Linux 6

Kernel	Minimum sensor version
3.8.13-16.1.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-16.2.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-16.2.2.el6uek.x86_64	Falcon sensor v4.23.6903

3.8.13-16.2.3.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-16.3.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-16.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-26.1.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-26.2.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-26.2.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-26.2.3.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-26.2.4.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-26.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-35.1.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-35.1.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-35.1.3.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-35.3.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-35.3.3.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-35.3.4.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-35.3.5.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-35.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-44.1.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-44.1.3.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-44.1.4.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-44.1.5.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-44.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-55.1.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-55.1.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-55.1.5.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-55.1.8.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-55.2.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-55.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.1.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.1.3.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.2.2.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.2.2.3.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.2.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.3.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.3.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.3.3.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.3.4.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.3.5.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.1.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.1.2.el6uek.x86_64	Falcon sensor v4.23.6903

3.8.13-98.2.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.2.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.4.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.5.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.6.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.7.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.2.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.2.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.2.4.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.2.5.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.3.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.3.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.4.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.4.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.6.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.6.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.7.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.8.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.9.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.9.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.10.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.11.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.13.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.13.3.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.14.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.14.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.15.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.15.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.16.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.16.3.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.16.4.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.17.4.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.17.5.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.18.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.18.3.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.18.4.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.19.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.19.3.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.19.4.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.19.7.el6uek.x86_64	Falcon sensor v4.23.6903

3.8.13-118.19.10.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.19.12.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.20.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.20.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.20.3.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.20.6.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.20.7.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.21.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.21.4.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.22.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.23.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.24.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.24.2.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.24.3.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.25.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.26.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.27.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.28.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.29.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.30.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-32.1.2.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-32.2.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-32.2.3.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-32.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-37.2.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-37.2.2.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-37.3.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-37.4.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-37.5.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-37.6.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-37.6.2.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-37.6.3.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.6.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.9.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.10.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.13.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.14.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.16.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.17.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.19.el6uek.x86_64	Falcon sensor v4.23.6903

4.112-61.1.22.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-61.1.23.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-61.1.25.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-61.1.27.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-61.1.28.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-61.1.33.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-61.1.34.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-61.51.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-61.63.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-61.64.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-61.65.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-94.1.8.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-94.2.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-94.3.4.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-94.3.5.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-94.3.6.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-94.3.7.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-94.3.8.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-94.3.9.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-94.5.7.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-94.5.9.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-94.7.8.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-94.8.2.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-94.8.3.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-94.8.5.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-94.8.10.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-103.3.8.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-103.3.8.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-103.6.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-103.7.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-103.7.3.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-103.7.4.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-103.9.2.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-103.9.4.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-103.9.6.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-103.9.7.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-103.10.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-112.14.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-112.14.2.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-112.14.5.el6uek.x86_64	Falcon sensor v4.23.6903
4.112-112.14.10.el6uek.x86_64	Falcon sensor v4.23.6903

4.1.12-112.14.11.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-112.14.13.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-112.14.14.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-112.14.15.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-112.16.4.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-112.16.7.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-112.17.3.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.14.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.14.2.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.14.3.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.14.5.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.15.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.15.2.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.15.4.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.16.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.16.2.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.16.3.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.16.4.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.17.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.17.2.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.18.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.18.5.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.18.6.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.18.9.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.19.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.19.2.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.19.4.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.19.5.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.19.6.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.19.7.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.20.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.20.3.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.20.7.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.21.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.22.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.22.2.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.22.4.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.23.1.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.23.2.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.23.4.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.24.1.el6uek.x86_64	Falcon sensor v4.23.6903

4.1.12-124.24.3.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.24.5.el6uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.25.1.el6uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.31.1.el6uek.x86_64	Falcon sensor v4.24.7002
4.1.12-124.26.1.el6uek.x86_64	Falcon sensor v4.24.7002
4.1.12-124.26.3.el6uek.x86_64	Falcon sensor v4.24.7002
4.1.12-124.26.5.el6uek.x86_64	Falcon sensor v4.25.7103
4.1.12-124.26.7.el6uek.x86_64	Falcon sensor v4.25.7103
3.8.13-118.32.1.el6uek.x86_64	Falcon sensor v4.26.7203
4.1.12-124.26.10.el6uek.x86_64	Falcon sensor v4.28.7303
3.8.13-118.33.2.el6uek.x86_64	Falcon sensor v5.10.7403
3.8.13-118.34.1.el6uek.x86_64	Falcon sensor v5.10.7403
4.1.12-94.8.4.el6uek.x86_64	Falcon sensor v5.10.7403
4.1.12-124.26.12.el6uek.x86_64	Falcon sensor v5.10.7403
4.1.12-124.27.1.el6uek.x86_64	Falcon sensor v5.10.7403
4.1.12-124.27.2.el6uek.x86_64	Falcon sensor v5.11.7503
3.8.13-118.35.1.el6uek.x86_64	Falcon sensor v5.12.7602
3.8.13-118.35.2.el6uek.x86_64	Falcon sensor v5.12.7602
4.1.12-124.28.1.el6uek.x86_64	Falcon sensor v5.12.7602
4.1.12-124.28.3.el6uek.x86_64	Falcon sensor v5.12.7602
3.8.13-118.36.1.el6uek.x86_64	Falcon sensor v5.12.7603
4.1.12-61.47.1.el6uek.x86_64	Falcon sensor v5.12.7603
4.1.12-124.28.5.el6uek.x86_64	Falcon sensor v5.12.7603
4.1.12-124.28.6.el6uek.x86_64	Falcon sensor v5.14.7803
4.1.12-124.29.3.el6uek.x86_64	Falcon sensor v5.15.7901
3.8.13-118.37.1.el6uek.x86_64	Falcon sensor v5.16.8002
4.1.12-124.29.3.1.el6uek.x86_64	Falcon sensor v5.16.8002
4.1.12-124.29.4.1.el6uek.x86_64	Falcon sensor v5.16.8002
4.1.12-124.30.1.el6uek.x86_64	Falcon sensor v5.16.8002
3.8.13-118.38.1.el6uek.x86_64	Falcon sensor v5.17.8103
4.1.12-124.31.1.el6uek.x86_64	Falcon sensor v5.17.8103
4.1.12-124.31.1.1.el6uek.x86_64	Falcon sensor v5.18.8202
3.8.13-118.39.1.el6uek.x86_64	Falcon sensor v5.18.8203
4.1.12-124.32.1.el6uek.x86_64	Falcon sensor v5.18.8203
4.1.12-124.32.3.el6uek	Falcon sensor v5.20.8402
3.8.13-118.39.1.1.el6uek.x86_64	Falcon sensor v5.20.8406
3.8.13-118.40.1.el6uek	Falcon sensor v5.23.8701
4.1.12-124.33.4.el6uek	Falcon sensor v5.23.8701
3.8.13-118.41.1.el6uek.x86_64	Falcon sensor v5.23.8703
4.1.12-124.34.1.el6uek.x86_64	Falcon sensor v5.23.8703
3.8.13-118.42.1.el6uek.x86_64	Falcon sensor v5.25.8902

4.1.12-124.35.1.el6uek.x86_64	Falcon sensor v5.25.8902
4.1.12-124.35.2.el6uek.x86_64	Falcon sensor v5.25.8902
4.1.12-124.35.4.el6uek.x86_64	Falcon sensor v5.26.9003
4.1.12-124.32.3.2.el6uek.x86_64	Falcon sensor v5.27.9104
4.1.12-124.36.1.el6uek.x86_64	Falcon sensor v5.27.9104
4.1.12-124.36.1.1.el6uek.x86_64	Falcon sensor v5.27.9104
4.1.12-124.36.3.el6uek.x86_64	Falcon sensor v5.27.9104
4.1.12-124.36.4.el6uek.x86_64	Falcon sensor v5.27.9104
3.8.13-118.43.1.el6uek.x86_64	Falcon sensor v5.28.9205
4.1.12-124.37.1.el6uek.x86_64	Falcon sensor v5.28.9205
3.8.13-118.44.1.el6uek.x86_64	Falcon sensor v5.30.9508
4.1.12-124.38.1.el6uek.x86_64	Falcon sensor v5.30.9508
3.8.13-118.45.1.el6uek.x86_64	Falcon sensor v5.31.9607
4.1.12-124.39.1.el6uek.x86_64	Falcon sensor v5.31.9607
4.1.12-124.39.2.el6uek.x86_64	Falcon sensor v5.31.9607
4.1.12-124.39.5.1.el6uek.x86_64	Falcon sensor v5.33.9804
3.8.13-118.46.1.el6uek.x86_64	Falcon sensor v5.32.9705
4.1.12-124.39.2.1.el6uek.x86_64	Falcon sensor v5.32.9705
4.1.12-124.39.5.el6uek.x86_64	Falcon sensor v5.32.9705
3.8.13-118.47.1.el6uek.x86_64	Falcon sensor v5.33.9808
4.1.12-124.40.6.el6uek.x86_64	Falcon sensor v5.33.9808
3.8.13-118.47.2.el6uek.x86_64	Falcon sensor v5.34.9917
4.1.12-124.40.6.3.el6uek.x86_64	Falcon sensor v5.34.9917

Oracle Linux 7

Kernel	Minimum sensor version
3.8.13-35.3.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-35.3.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-35.3.3.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-35.3.4.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-35.3.5.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-44.1.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-44.1.3.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-44.1.4.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-44.1.5.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-44.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-55.1.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-55.1.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-55.1.5.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-55.1.6.el7uek.x86_64	Falcon sensor v4.23.6903

3.8.13-55.1.8.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-55.2.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-55.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.1.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.1.3.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.2.2.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.2.2.3.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.2.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.3.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.3.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.3.3.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.3.4.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.3.5.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-68.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.1.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.1.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.2.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.2.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.4.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.5.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.6.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.7.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-98.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.2.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.2.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.2.4.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.2.5.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.3.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.3.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.4.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.4.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.6.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.6.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.7.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.8.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.9.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.9.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.10.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.11.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.13.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.13.3.el7uek.x86_64	Falcon sensor v4.23.6903

3.8.13-118.14.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.14.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.15.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.15.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.15.3.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.16.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.16.3.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.16.4.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.17.4.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.17.5.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.18.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.18.3.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.18.4.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.19.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.19.3.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.19.4.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.19.7.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.19.10.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.19.12.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.20.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.20.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.20.3.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.20.6.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.20.7.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.21.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.21.4.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.22.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.23.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.24.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.24.2.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.24.3.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.25.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.26.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.27.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.28.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.29.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.30.1.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-32.1.2.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-32.2.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-32.2.3.el7uek.x86_64	Falcon sensor v4.23.6903

4.1.12-32.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-37.2.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-37.2.2.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-37.3.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-37.4.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-37.5.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-37.6.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-37.6.2.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-37.6.3.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.6.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.9.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.10.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.13.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.14.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.16.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.17.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.18.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.19.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.22.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.23.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.24.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.25.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.27.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.28.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.33.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.1.34.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.51.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.63.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.64.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-61.65.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-94.1.8.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-94.2.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-94.3.4.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-94.3.5.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-94.3.6.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-94.3.7.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-94.3.8.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-94.3.9.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-94.5.7.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-94.5.9.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-94.7.8.el7uek.x86_64	Falcon sensor v4.23.6903

4.112-94.8.2.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-94.8.3.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-94.8.5.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-94.8.10.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-103.3.8.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-103.3.8.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-103.6.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-103.7.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-103.7.3.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-103.7.4.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-103.9.2.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-103.9.4.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-103.9.6.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-103.9.7.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-103.10.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-112.14.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-112.14.2.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-112.14.5.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-112.14.10.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-112.14.11.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-112.14.13.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-112.14.14.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-112.14.15.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-112.16.4.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-112.16.7.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-112.17.3.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-124.14.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-124.14.2.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-124.14.3.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-124.14.5.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-124.15.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-124.15.2.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-124.15.4.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-124.16.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-124.16.2.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-124.16.3.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-124.16.4.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-124.17.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-124.17.2.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-124.18.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.112-124.18.5.el7uek.x86_64	Falcon sensor v4.23.6903

4.1.12-124.18.6.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.18.9.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.19.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.19.2.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.19.4.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.19.5.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.19.6.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.19.7.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.20.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.20.3.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.20.7.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.21.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.22.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.22.2.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.22.4.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.23.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.23.2.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.23.4.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.24.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.24.3.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.24.5.el7uek.x86_64	Falcon sensor v4.23.6903
4.1.12-124.25.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.14.35-1818.0.9.el7uek.x86_64	Falcon sensor v4.23.6903
4.14.35-1818.0.14.el7uek.x86_64	Falcon sensor v4.23.6903
4.14.35-1818.1.6.el7uek.x86_64	Falcon sensor v4.23.6903
4.14.35-1818.2.1.el7uek.x86_64	Falcon sensor v4.23.6903
4.14.35-1818.3.3.el7uek.x86_64	Falcon sensor v4.23.6903
4.14.35-1818.4.5.el7uek.x86_64	Falcon sensor v4.23.6903
4.14.35-1818.4.6.el7uek.x86_64	Falcon sensor v4.23.6903
4.14.35-1818.4.7.el7uek.x86_64	Falcon sensor v4.23.6903
4.14.35-1818.5.4.el7uek.x86_64	Falcon sensor v4.23.6903
4.14.35-1844.0.7.el7uek.x86_64	Falcon sensor v4.23.6903
4.14.35-1844.1.3.el7uek.x86_64	Falcon sensor v4.23.6903
4.14.35-1844.2.5.el7uek.x86_64	Falcon sensor v4.23.6903
3.8.13-118.31.1.el7uek.x86_64	Falcon sensor v4.24.7002
4.1.12-124.26.1.el7uek.x86_64	Falcon sensor v4.24.7002
4.1.12-124.26.3.el7uek.x86_64	Falcon sensor v4.24.7002
4.14.35-1844.3.2.el7uek.x86_64	Falcon sensor v4.24.7002
4.1.12-124.26.5.el7uek.x86_64	Falcon sensor v4.25.7103
4.1.12-124.26.7.el7uek.x86_64	Falcon sensor v4.25.7103
3.8.13-118.32.1.el7uek.x86_64	Falcon sensor v4.26.7203

4.14.35-1844.4.5.el7uek.x86_64	Falcon sensor v4.26.7203
4.1.12-124.26.10.el7uek.x86_64	Falcon sensor v4.28.7303
3.8.13-118.33.2.el7uek.x86_64	Falcon sensor v5.10.7403
3.8.13-118.34.1.el7uek.x86_64	Falcon sensor v5.10.7403
4.1.12-94.8.4.el7uek.x86_64	Falcon sensor v5.10.7403
4.1.12-124.26.12.el7uek.x86_64	Falcon sensor v5.10.7403
4.1.12-124.27.1.el7uek.x86_64	Falcon sensor v5.10.7403
4.14.35-1844.4.5.2.el7uek.x86_64	Falcon sensor v5.10.7403
4.14.35-1844.5.3.el7uek.x86_64	Falcon sensor v5.10.7403
4.1.12-124.27.2.el7uek.x86_64	Falcon sensor v5.11.7503
4.14.35-1902.0.18.el7uek.x86_64	Falcon sensor v5.11.7503
3.8.13-118.35.1.el7uek.x86_64	Falcon sensor v5.12.7602
3.8.13-118.35.2.el7uek.x86_64	Falcon sensor v5.12.7602
4.1.12-124.28.1.el7uek.x86_64	Falcon sensor v5.12.7602
4.1.12-124.28.3.el7uek.x86_64	Falcon sensor v5.12.7602
4.14.35-1902.2.0.el7uek.x86_64	Falcon sensor v5.12.7602
4.1.12-124.28.5.el7uek.x86_64	Falcon sensor v5.12.7603
4.14.35-1902.3.1.el7uek.x86_64	Falcon sensor v5.12.7603
3.8.13-118.36.1.el7uek.x86_64	Falcon sensor v5.14.7803
4.1.12-124.28.6.el7uek.x86_64	Falcon sensor v5.14.7803
4.1.12-124.29.3.el7uek.x86_64	Falcon sensor v5.15.7901
4.1.12-124.29.4.1.el7uek.x86_64	Falcon sensor v5.16.8002
4.1.12-124.30.1.el7uek.x86_64	Falcon sensor v5.16.8002
3.8.13-118.37.1.el7uek.x86_64	Falcon sensor v5.16.8002
4.1.12-124.29.3.1.el7uek.x86_64	Falcon sensor v5.16.8002
4.14.35-1902.3.2.el7uek.x86_64	Falcon sensor v5.16.8002
4.14.35-1902.4.8.el7uek.x86_64	Falcon sensor v5.17.8101
3.8.13-118.38.1.el7uek.x86_64	Falcon sensor v5.17.8103
4.1.12-124.31.1.el7uek.x86_64	Falcon sensor v5.17.8103
4.14.35-1902.5.2.el7uek.x86_64	Falcon sensor v5.18.8201
4.1.12-124.31.1.1.el7uek.x86_64	Falcon sensor v5.18.8202
4.14.35-1902.5.2.1.el7uek.x86_64	Falcon sensor v5.18.8202
4.14.35-1902.5.2.2.el7uek.x86_64	Falcon sensor v5.18.8202
3.8.13-118.39.1.el7uek.x86_64	Falcon sensor v5.18.8203
4.1.12-124.32.1.el7uek.x86_64	Falcon sensor v5.18.8203
4.14.35-1902.5.1.5.el7uek.x86_64	Falcon sensor v5.20.8406
3.8.13-118.39.1.1.el7uek.x86_64	Falcon sensor v5.20.8406
3.8.13-118.40.1.el7uek	Falcon sensor v5.23.8701
4.1.12-124.33.4.el7uek	Falcon sensor v5.23.8701
4.14.35-1902.7.3.1.el7uek	Falcon sensor v5.23.8701
3.8.13-118.41.1.el7uek.x86_64	Falcon sensor v5.23.8703

4.1.12-124.34.1.el7uek.x86_64	Falcon sensor v5.23.8703
4.14.35-1902.8.4.el7uek.x86_64	Falcon sensor v5.23.8705
4.14.35-1902.5.1.4.el7uek.x86_64	Falcon sensor v5.23.8706
3.8.13-118.42.1.el7uek.x86_64	Falcon sensor v5.25.8902
4.1.12-124.35.1.el7uek.x86_64	Falcon sensor v5.25.8902
4.1.12-124.35.2.el7uek.x86_64	Falcon sensor v5.25.8902
4.14.35-1902.9.2.el7uek.x86_64	Falcon sensor v5.25.8902
4.1.12-124.35.4.el7uek.x86_64	Falcon sensor v5.26.9003
4.14.35-1902.10.2.1.el7uek.x86_64	Falcon sensor v5.26.9003
4.14.35-1902.10.4.el7uek.x86_64	Falcon sensor v5.26.9003
4.14.35-1902.10.4.1.el7uek.x86_64	Falcon sensor v5.26.9003
4.14.35-1902.10.7.el7uek.x86_64	Falcon sensor v5.27.9101
4.1.12-124.32.3.2.el7uek.x86_64	Falcon sensor v5.27.9104
4.1.12-124.36.1.el7uek.x86_64	Falcon sensor v5.27.9104
4.1.12-124.36.1.1.el7uek.x86_64	Falcon sensor v5.27.9104
4.1.12-124.36.3.el7uek.x86_64	Falcon sensor v5.27.9104
4.1.12-124.36.4.el7uek.x86_64	Falcon sensor v5.27.9104
4.14.35-1902.10.4.2.el7uek.x86_64	Falcon sensor v5.27.9104
4.14.35-1902.7.3.el7uek.x86_64	Falcon sensor v5.27.9104
4.14.35-1902.10.8.el7uek.x86_64	Falcon sensor v5.27.9104
3.8.13-118.43.1.el7uek.x86_64	Falcon sensor v5.28.9205
4.1.12-124.37.1.el7uek.x86_64	Falcon sensor v5.28.9205
4.14.35-1902.11.3.el7uek.x86_64	Falcon sensor v5.29.9402
4.14.35-1902.11.3.1.el7uek.x86_64	Falcon sensor v5.29.9403
4.14.35-1902.300.11.el7uek.x86_64	Falcon sensor v5.29.9403
3.8.13-118.44.1.el7uek.x86_64	Falcon sensor v5.30.9508
4.1.12-124.38.1.el7uek.x86_64	Falcon sensor v5.30.9508
4.14.35-1902.301.1.el7uek.x86_64	Falcon sensor v5.30.9508
3.8.13-118.45.1.el7uek.x86_64	Falcon sensor v5.31.9607
4.1.12-124.39.1.el7uek.x86_64	Falcon sensor v5.31.9607
4.1.12-124.39.2.el7uek.x86_64	Falcon sensor v5.31.9607
4.14.35-1902.302.2.el7uek.x86_64	Falcon sensor v5.31.9607
4.1.12-124.39.5.1.el7uek.x86_64	Falcon sensor v5.33.9804
4.14.35-1902.303.4.1.el7uek.x86_64	Falcon sensor v5.33.9804
3.8.13-118.46.1.el7uek.x86_64	Falcon sensor v5.32.9705
4.1.12-124.39.2.1.el7uek.x86_64	Falcon sensor v5.32.9705
4.1.12-124.39.5.el7uek.x86_64	Falcon sensor v5.32.9705
4.14.35-1902.303.5.3.el7uek.x86_64	Falcon sensor v5.33.9806
3.8.13-118.47.1.el7uek.x86_64	Falcon sensor v5.33.9808
4.1.12-124.40.6.el7uek.x86_64	Falcon sensor v5.33.9808
4.14.35-1902.304.6.el7uek.x86_64	Falcon sensor v5.33.9808

3.8.13-118.47.2.el7uek.x86_64	Falcon sensor v5.34.9917
4.1.12-124.40.6.3.el7uek.x86_64	Falcon sensor v5.34.9917
4.14.35-1902.304.6.3.el7uek.x86_64	Falcon sensor v5.34.9917

RHEL 6 / CentOS 6

Kernel	Minimum sensor version
2.6.32-573.el6.x86_64	Earlier than v3.4
2.6.32-573.1.1.el6.x86_64	Earlier than v3.4
2.6.32-573.3.1.el6.x86_64	Earlier than v3.4
2.6.32-573.7.1.el6.x86_64	Earlier than v3.4
2.6.32-573.8.1.el6.x86_64	Earlier than v3.4
2.6.32-573.12.1.el6.x86_64	Earlier than v3.4
2.6.32-573.18.1.el6.x86_64	Earlier than v3.4
2.6.32-573.22.1.el6.x86_64	Earlier than v3.4
2.6.32-573.26.1.el6.x86_64	Earlier than v3.4
2.6.32-573.30.1.el6.x86_64	Earlier than v3.4
2.6.32-573.32.1.el6.x86_64	Earlier than v3.4
2.6.32-573.34.1.el6.x86_64	Earlier than v3.4
2.6.32-573.35.1.el6.x86_64	Earlier than v3.4
2.6.32-573.35.2.el6.x86_64	Earlier than v3.4
2.6.32-573.37.1.el6.x86_64	Earlier than v3.4
2.6.32-573.38.1.el6.x86_64	Earlier than v3.4
2.6.32-573.40.1.el6.x86_64	Earlier than v3.4
2.6.32-573.42.2.el6.x86_64	Falcon sensor v3.4
2.6.32-573.43.2.el6.x86_64	Falcon sensor v3.4
2.6.32-573.43.3.el6.x86_64	Falcon sensor v3.7
2.6.32-573.45.1.el6.x86_64	Falcon sensor v3.7
2.6.32-573.45.2.el6.x86_64	Falcon sensor v3.7
2.6.32-573.47.1.el6.x86_64	Falcon sensor v3.7
2.6.32-573.48.1.el6.x86_64	Falcon sensor v3.7
2.6.32-573.49.1.el6.x86_64	Falcon sensor v3.8
2.6.32-573.49.3.el6.x86_64	Falcon sensor v3.10.4204
2.6.32-573.51.1.el6.x86_64	Falcon sensor v4.1.4404
2.6.32-642.el6.x86_64	Earlier than v3.4
2.6.32-642.1.1.el6.x86_64	Earlier than v3.4
2.6.32-642.3.1.el6.x86_64	Earlier than v3.4
2.6.32-642.4.2.el6.x86_64	Earlier than v3.4
2.6.32-642.6.1.el6.x86_64	Earlier than v3.4
2.6.32-642.6.2.el6.x86_64	Earlier than v3.4
2.6.32-642.11.1.el6.x86_64	Earlier than v3.4

2.6.32-642.13.1.el6.x86_64	Earlier than v3.4
2.6.32-642.13.2.el6.x86_64	Earlier than v3.4
2.6.32-642.15.1.el6.x86_64	Earlier than v3.4
2.6.32-696.el6.x86_64	Falcon sensor v3.4
2.6.32-696.1.1.el6.x86_64	Falcon sensor v3.4
2.6.32-696.3.1.el6.x86_64	Falcon sensor v3.4
2.6.32-696.3.2.el6.x86_64	Falcon sensor v3.4
2.6.32-696.6.3.el6.x86_64	Falcon sensor v3.5
2.6.32-696.10.1.el6.x86_64	Falcon sensor v3.6
2.6.32-696.10.2.el6.x86_64	Falcon sensor v3.7
2.6.32-696.10.3.el6.x86_64	Falcon sensor v3.7
2.6.32-696.18.7.el6.x86_64	Falcon sensor v3.8
2.6.32-696.13.2.el6.x86_64	Falcon sensor v3.10.4204
2.6.32-696.16.1.el6.x86_64	Falcon sensor v3.10.4204
2.6.32-696.20.1.el6.x86_64	Falcon sensor v3.10.4205
2.6.32-573.41.1.el6.x86_64	Falcon sensor v4.5.5011
2.6.32-573.42.1.el6.x86_64	Falcon sensor v4.5.5011
2.6.32-573.53.1.el6.x86_64	Falcon sensor v4.5.5013
2.6.32-696.23.1.el6.x86_64	Falcon sensor v4.5.5013
2.6.32-696.28.1.el6.x86_64	Falcon sensor v4.5.5013
2.6.32-696.30.1.el6.x86_64	Falcon sensor v4.5.5013
2.6.32-573.55.2.el6.x86_64	Falcon sensor v4.5.5014
2.6.32-573.55.4.el6.x86_64	Falcon sensor v4.5.5014
2.6.32-573.59.1.el6.x86_64	Falcon sensor v4.8.5305
6.7 - 2.6.32-573.60.1.el6.x86_64	Falcon sensor v4.11.5605
6.10 - 2.6.32-754.el6.x86_64	Falcon sensor v4.11.5605
6.10 - 2.6.32-754.2.1.el6.x86_64	Falcon sensor v4.11.5605
6.7 - 2.6.32-573.60.4.el6.x86_64	Falcon sensor v4.11.5609
6.10 - 2.6.32-754.3.5.el6.x86_64	Falcon sensor v4.11.5609
6.7 - 2.6.32-573.62.1.el6.x86_64	Falcon sensor v4.13.5803
2.6.32-754.6.3.el6.x86_64	Falcon sensor v4.16.6101
2.6.32-573.65.2.el6.x86_64	Falcon sensor v4.16.6106
2.6.32-754.9.1.el6.x86_64	Falcon sensor v4.18.6402
2.6.32-754.10.1.el6.x86_64	Falcon sensor v4.20.6602
2.6.32-754.11.1.el6.x86_64	Falcon sensor v4.23.6903
2.6.32-754.12.1.el6.x86_64	Falcon sensor v4.26.7203
2.6.32-754.14.2.el6.x86_64	Falcon sensor v5.10.7403
2.6.32-754.15.3.el6.x86_64	Falcon sensor v5.12.7602
2.6.32-754.17.1.el6.x86_64	Falcon sensor v5.12.7603
2.6.32-754.18.2.el6.x86_64	Falcon sensor v5.16.8002
2.6.32-754.22.1.el6.x86_64	Falcon sensor v5.18.8201

2.6.32-754.23.1.el6.x86_64	Falcon sensor v5.18.8202
2.6.32-754.24.2.el6.x86_64	Falcon sensor v5.20.8406
2.6.32-754.24.3.el6.x86_64	Falcon sensor v5.20.8406
2.6.32-754.25.1.el6.x86_64	Falcon sensor v5.23.8705
2.6.32-754.27.1.el6.x86_64	Falcon sensor v5.26.9003
2.6.32-754.28.1.el6.x86_64	Falcon sensor v5.29.9402
2.6.32-754.29.1.el6.x86_64	Falcon sensor v5.30.9510
2.6.32-754.29.2.el6.x86_64	Falcon sensor v5.31.9607
2.6.32-754.30.2.el6.x86_64	Falcon sensor v5.33.9804

RHEL 7 / CentOS 7

Kernel	Minimum sensor version
3.10.0-229.el7.x86_64	Earlier than v3.4
3.10.0-229.1.2.el7.x86_64	Earlier than v3.4
3.10.0-229.4.2.el7.x86_64	Earlier than v3.4
3.10.0-229.7.2.el7.x86_64	Earlier than v3.4
3.10.0-229.11.1.el7.x86_64	Earlier than v3.4
3.10.0-229.14.1.el7.x86_64	Earlier than v3.4
3.10.0-229.20.1.el7.x86_64	Earlier than v3.4
3.10.0-229.24.2.el7.x86_64	Earlier than v3.4
3.10.0-229.26.2.el7.x86_64	Earlier than v3.4
3.10.0-229.28.1.el7.x86_64	Earlier than v3.4
3.10.0-229.30.1.el7.x86_64	Falcon sensor v3.5
3.10.0-229.34.1.el7.x86_64	Earlier than v3.4
3.10.0-229.38.1.el7.x86_64	Earlier than v3.4
3.10.0-229.40.1.el7.x86_64	Earlier than v3.4
3.10.0-229.42.1.el7.x86_64	Earlier than v3.4
3.10.0-229.42.2.el7.x86_64	Earlier than v3.4
3.10.0-229.44.1.el7.x86_64	Earlier than v3.4
3.10.0-229.46.1.el7.x86_64	Earlier than v3.4
3.10.0-229.48.1.el7.x86_64	Earlier than v3.4
3.10.0-229.49.1.el7.x86_64	Earlier than v3.4
3.10.0-327.el7.x86_64	Earlier than v3.4
3.10.0-327.3.1.el7.x86_64	Earlier than v3.4
3.10.0-327.4.4.el7.x86_64	Earlier than v3.4
3.10.0-327.4.5.el7.x86_64	Earlier than v3.4
3.10.0-327.10.1.el7.x86_64	Earlier than v3.4
3.10.0-327.13.1.el7.x86_64	Earlier than v3.4
3.10.0-327.18.2.el7.x86_64	Earlier than v3.4
3.10.0-327.22.2.el7.x86_64	Earlier than v3.4

3.10.0-327.28.2.el7.x86_64	Earlier than v3.4
3.10.0-327.28.3.el7.x86_64	Earlier than v3.4
3.10.0-327.36.1.el7.x86_64	Earlier than v3.4
3.10.0-327.36.2.el7.x86_64	Earlier than v3.4
3.10.0-327.36.3.el7.x86_64	Earlier than v3.4
3.10.0-327.41.3.el7.x86_64	Earlier than v3.4
3.10.0-327.41.4.el7.x86_64	Earlier than v3.4
3.10.0-327.44.2.el7.x86_64	Earlier than v3.4
3.10.0-327.46.1.el7.x86_64	Earlier than v3.4
3.10.0-327.49.2.el7.x86_64	Earlier than v3.4
3.10.0-327.53.1.el7.x86_64	Falcon sensor v3.5
3.10.0-327.55.1.el7.x86_64	Falcon sensor v3.5
3.10.0-327.55.2.el7.x86_64	Falcon sensor v3.4
3.10.0-327.55.3.el7.x86_64	Falcon sensor v3.5
3.10.0-327.58.1.el7.x86_64	Falcon sensor v3.5
3.10.0-327.59.1.el7.x86_64	Falcon sensor v3.6
3.10.0-327.59.2.el7.x86_64	Falcon sensor v3.7
3.10.0-327.59.3.el7.x86_64	Falcon sensor v3.7
3.10.0-327.61.3.el7.x86_64	Falcon sensor v3.10.4204
3.10.0-327.62.1.el7.x86_64	Falcon sensor v3.10.4204
3.10.0-514.el7.x86_64	Earlier than v3.4
3.10.0-514.2.2.el7.x86_64	Earlier than v3.4
3.10.0-514.6.1.el7.x86_64	Earlier than v3.4
3.10.0-514.6.2.el7.x86_64	Falcon sensor v3.5
3.10.0-514.10.2.el7.x86_64	Earlier than v3.4
3.10.0-514.16.1.el7.x86_64	Falcon sensor v3.4
3.10.0-514.21.1.el7.x86_64	Falcon sensor v3.4
3.10.0-514.21.2.el7.x86_64	Falcon sensor v3.4
3.10.0-514.26.1.el7.x86_64	Falcon sensor v3.4
3.10.0-514.26.2.el7.x86_64	Falcon sensor v3.5
3.10.0-514.28.1.el7.x86_64	Falcon sensor v3.6
3.10.0-514.28.2.el7.x86_64	Falcon sensor v3.7
3.10.0-514.32.2.el7.x86_64	Falcon sensor v3.7
3.10.0-514.32.3.el7.x86_64	Falcon sensor v3.7
3.10.0-514.35.1.el7.x86_64	Falcon sensor v3.10.4204
3.10.0-514.36.1.el7.x86_64	Falcon sensor v3.8
3.10.0-514.36.5.el7.x86_64	Falcon sensor v3.8
3.10.0-514.35.1.el7.x86_64	Falcon sensor v3.10.4204
3.10.0-514.41.1.el7.x86_64	Falcon sensor v3.10.4205
3.10.0-693.el7.x86_64	Falcon sensor v3.6
3.10.0-693.1.1.el7.x86_64	Falcon sensor v3.6

3.10.0-693.2.1.el7.x86_64	Falcon sensor v3.6
3.10.0-693.2.2.el7.x86_64	Falcon sensor v3.7
3.10.0-693.5.2.el7.x86_64	Falcon sensor v3.10.4204
3.10.0-693.11.6.el7.x86_64	Falcon sensor v3.8
3.10.0-693.11.1.el7.x86_64	Falcon sensor v3.10.4204
3.10.0-693.17.1.el7.x86_64	Falcon sensor v3.10.4205
3.10.0-514.44.1.el7.x86_64	Falcon sensor v4.3.4603
3.10.0-693.21.1.el7.x86_64	Falcon sensor v4.3.4603
3.10.0-514.48.1.el7.x86_64	Falcon sensor v4.5.5011
3.10.0-693.25.2.el7.x86_64	Falcon sensor v4.5.5011
7.5 3.10.0-862.el7.x86_64	Falcon sensor v4.5.5011
7.3 3.10.0-514.48.3.el7.x86_64	Falcon sensor v4.5.5014
7.3 3.10.0-514.48.5.el7.x86_64	Falcon sensor v4.5.5014
7.3 3.10.0-514.51.1.el7.x86_64	Falcon sensor v4.5.5014
7.4 3.10.0-693.25.4.el7.x86_64	Falcon sensor v4.5.5014
7.4 3.10.0-693.25.7.el7.x86_64	Falcon sensor v4.5.5014
7.4 3.10.0-693.33.1.el7.x86_64	Falcon sensor v4.5.5014
7.5 3.10.0-862.2.3.el7.x86_64	Falcon sensor v4.5.5014
7.5 3.10.0-862.3.2.el7.x86_64	Falcon sensor v4.5.5014
7.5 3.10.0-862.3.3.el7.x86_64	Falcon sensor v4.5.5501
7.3 3.10.0-514.53.1.el7.x86_64	Falcon sensor v4.11.5605
7.4 3.10.0-693.35.1.el7.x86_64	Falcon sensor v4.11.5605
7.5 3.10.0-862.9.1.el7.x86_64	Falcon sensor v4.11.5605
7.3 - 3.10.0-514.55.4.el7.x86_64	Falcon sensor v4.11.5609
7.4 - 3.10.0-693.37.4.el7.x86_64	Falcon sensor v4.11.5609
7.5 - 3.10.0-862.11.6.el7.x86_64	Falcon sensor v4.11.5609
3.10.0-862.14.4.el7.x86_64	Falcon sensor v4.13.5806
3.10.0-693.39.1.el7.x86_64	Falcon sensor v4.13.5806
3.10.0-514.58.1.el7.x86_64	Falcon sensor v4.13.5806
3.10.0-514.61.1.el7.x86_64	Falcon sensor v4.16.6109
3.10.0-693.43.1.el7.x86_64	Falcon sensor v4.16.6109
3.10.0-862.20.2.el7.x86_64	Falcon sensor v4.16.6109
3.10.0-957.el7.x86_64	Falcon sensor v4.18.6401
3.10.0-957.1.3.el7.x86_64	Falcon sensor v4.18.6401
3.10.0-862.25.3.el7.x86_64	Falcon sensor v4.20.6602
3.10.0-862.27.1.el7.x86_64	Falcon sensor v4.21.6705
3.10.0-957.5.1.el7.x86_64	Falcon sensor v4.21.6705
3.10.0-693.44.1.el7.x86_64	Falcon sensor v4.22.6805
3.10.0-862.29.1.el7.x86_64	Falcon sensor v4.24.7002
3.10.0-957.10.1.el7.x86_64	Falcon sensor v4.24.7002
3.10.0-693.46.1.el7.x86_64	Falcon sensor v4.25.7103

3.10.0-862.32.1.el7.x86_64	Falcon sensor v4.28.7303
3.10.0-957.12.1.el7.x86_64	Falcon sensor v4.28.7303
3.10.0-693.47.2.el7.x86_64	Falcon sensor v5.10.7403
3.10.0-862.32.2.el7.x86_64	Falcon sensor v5.10.7403
3.10.0-957.12.2.el7.x86_64	Falcon sensor v5.10.7403
3.10.0-693.50.3.el7.x86_64	Falcon sensor v5.12.7602
3.10.0-862.34.1.el7.x86_64	Falcon sensor v5.12.7602
3.10.0-862.34.2.el7.x86_64	Falcon sensor v5.12.7602
3.10.0-957.21.2.el7.x86_64	Falcon sensor v5.12.7602
3.10.0-957.21.3.el7.x86_64	Falcon sensor v5.12.7602
3.10.0-862.37.1.el7.x86_64	Falcon sensor v5.14.7803
3.10.0-957.27.2.el7.x86_64	Falcon sensor v5.15.7901
3.10.0-1062.el7.x86_64	Falcon sensor v5.16.8002
3.10.0-957.27.4.el7.x86_64	Falcon sensor v5.16.8002
3.10.0-693.55.1.el7.x86_64	Falcon sensor v5.16.8002
3.10.0-862.41.1.el7.x86_64	Falcon sensor v5.17.8103
3.10.0-1062.1.1.el7.x86_64	Falcon sensor v5.17.8103
3.10.0-693.58.1.el7.x86_64	Falcon sensor v5.18.8201
3.10.0-1062.1.2.el7.x86_64	Falcon sensor v5.18.8202
4.1.12-124.32.3.el7uek	Falcon sensor 5.20.8402
4.14.35-1902.6.6.el7uek	Falcon sensor 5.20.8402
3.10.0-862.41.2.el7.x86_64	Falcon sensor v5.20.8404
3.10.0-862.43.1.el7.x86_64	Falcon sensor v5.20.8404
3.10.0-957.35.1.el7.x86_64	Falcon sensor v5.20.8404
3.10.0-957.35.2.el7.x86_64	Falcon sensor v5.20.8404
3.10.0-957.38.1.el7.x86_64	Falcon sensor v5.20.8404
3.10.0-1062.4.1.el7.x86_64	Falcon sensor v5.20.8404
3.10.0-862.43.2.el7.x86_64	Falcon sensor v5.20.8406
3.10.0-862.43.3.el7.x86_64	Falcon sensor v5.20.8406
3.10.0-957.38.3.el7.x86_64	Falcon sensor v5.20.8406
3.10.0-1062.4.3.el7.x86_64	Falcon sensor v5.20.8406
3.10.0-862.44.2.el7.x86_64	Falcon sensor v5.23.8703
3.10.0-1062.7.1.el7.x86_64	Falcon sensor v5.23.8703
3.10.0-1062.9.1.el7.x86_64	Falcon sensor v5.23.8703
3.10.0-957.41.1.el7.x86_64	Falcon sensor v5.23.8703
3.10.0-862.46.1.el7.x86_x64	Falcon sensor v5.23.8706
3.10.0-957.43.1.el7.x86_64	Falcon sensor v5.26.9003
3.10.0-1062.12.1.el7.x86_64	Falcon sensor v5.26.9003
3.10.0-862.48.1.el7.x86_64	Falcon sensor v5.27.9104
3.10.0-957.38.2.el7.x86_64	Falcon sensor v5.27.9104
3.10.0-1062.4.2.el7.x86_64	Falcon sensor v5.27.9104

3.10.0-1062.18.1.el7.x86_64	Falcon sensor v5.29.9402
3.10.0-957.46.1.el7.x86_64	Falcon sensor v5.27.9105
3.10.0-862.51.1.el7.x86_64	Falcon sensor v5.30.9507
3.10.0-1127.el7.x86_64	Falcon sensor v5.30.9510
3.10.0-1127.8.2.el7.x86_64	Falcon sensor v5.31.9607
3.10.0-1062.26.1.el7.x86_64	Falcon sensor v5.33.9804
3.10.0-1062.21.1.el7.x86_64	Falcon sensor v5.32.9705
3.10.0-1127.10.1.el7.x86_64	Falcon sensor v5.32.9705
3.10.0-957.48.1.el7.x86_64	Falcon sensor v5.32.9705
3.10.0-957.54.1.el7.x86_64	Falcon sensor v5.32.9705
3.10.0-1127.13.1.el7.x86_64	Falcon sensor v5.33.9806
3.10.0-1062.30.1.el7.x86_64	Falcon sensor v5.34.9917
3.10.0-957.56.1.el7.x86_64	Falcon sensor v5.34.9917
3.10.0-957.58.2.el7.x86_64	Falcon sensor v5.34.9917
3.10.0-1062.31.2.el7.x86_64	Falcon sensor v5.34.9917
3.10.0-1127.18.2.el7.x86_64	Falcon sensor v5.34.9917

RHEL 8 / CentOS 8

Kernel	Minimum sensor version
4.18.0-80.el8.x86_64	Falcon sensor v5.11.7503
4.18.0-80.1.2.el8_0.x86_64	Falcon sensor v5.11.7503
4.18.0-80.4.2.el8_0.x86_64	Falcon sensor v5.12.7602
4.18.0-80.7.1.el8_0.x86_64	Falcon sensor v5.16.8002
4.18.0-80.7.2.el8_0.x86_64	Falcon sensor v5.16.8002
4.18.0-80.11.1.el8_0.x86_64	Falcon sensor v5.18.8201
4.18.0-80.11.2.el8_0.x86_64	Falcon sensor v5.18.8202
4.18.0-147.el8.x86_64	Falcon sensor v5.27.9101
4.18.0-147.0.2.el8_1.x86_64	Falcon sensor v5.27.9101
4.18.0-147.0.3.el8_1.x86_64	Falcon sensor v5.27.9101
4.18.0-147.3.1.el8_1.x86_64	Falcon sensor v5.27.9101
4.18.0-147.5.1.el8_1.x86_64	Falcon sensor v5.27.9101
4.18.0-147.8.1.el8_1.x86_64	Falcon sensor v5.30.9507
4.18.0-147.20.1.el8_1.x86_64	Falcon sensor v5.33.9806
4.18.0-193.el8.x86_64	Falcon sensor v5.34.9917

RHEL/CentOS 8.1

Kernel	Minimum sensor version
4.18.0-147.13.2.el8_1.x86_64	Falcon sensor v5.32.9705
4.18.0-147.24.2.el8_1.x86_64	Falcon sensor v5.34.9917

RHEL/CentOS 8.2

Kernel	Minimum sensor version
4.18.0-193.1.2.el8_2.x86_64	Falcon sensor v5.34.9917
4.18.0-193.6.3.el8_2.x86_64	Falcon sensor v5.34.9917
4.18.0-193.13.2.el8_2.x86_64	Falcon sensor v5.34.9917
4.18.0-193.14.3.el8_2.x86_64	Falcon sensor v5.34.9917

SLES 11 SP1

Kernel	Minimum sensor version
3.0.101-108.38-default	Falcon sensor v4.5.5011

SLES 11 SP4

Kernel	Minimum sensor version
3.0.101-63-default	Earlier than v3.4
3.0.101-65-default	Earlier than v3.4
3.0.101-68-default	Earlier than v3.4
3.0.101-71-default	Earlier than v3.4
3.0.101-77-default	Earlier than v3.4
3.0.101-80-default	Earlier than v3.4
3.0.101-84-default	Earlier than v3.4
3.0.101-88-default	Earlier than v3.4
3.0.101-91-default	Earlier than v3.4
3.0.101-94-default	Earlier than v3.4
3.0.101-97-default	Falcon sensor v3.5
3.0.101-100-default	Falcon sensor v3.4
3.0.101-104-default	Falcon sensor v3.5
3.0.101-107-default	Falcon sensor v3.4
3.0.101-108.7-default	Falcon sensor v3.7
3.0.101-108.10-default	Falcon sensor v3.7
3.0.101-108.13-default	Falcon sensor v3.10.4204
3.0.101-108.18-default	Falcon sensor v3.8
3.0.101-108.21-default	Falcon sensor v3.8
3.0.101-108.35-default	Falcon sensor v4.1.4404
3.0.101-108.41-default	Falcon sensor v4.5.5014
3.0.101-108.48-default	Falcon sensor v4.5.5014
3.0.101-108.52-default	Falcon sensor v4.8.5305
3.0.101-108.57-default	Falcon sensor v4.11.5605

3.0.101-108.60-default	Falcon sensor v4.11.5605
3.0.101-108.63-default	Falcon sensor v4.11.5607
3.0.101-108.68-default	Falcon sensor v4.11.5609
3.0.101-108.71-default	Falcon sensor v4.13.5806
3.0.101-108.74-default	Falcon sensor v4.13.5809
3.0.101-108.77-default	Falcon sensor v4.16.6101
3.0.101-108.81-default	Falcon sensor v4.16.6109
3.0.101-108.84-default	Falcon sensor v4.18.6402
3.0.101-108.87-default	Falcon sensor v4.24.7002
3.0.101-108.90-default	Falcon sensor v5.14.7803
3.0.101-108.95-default	Falcon sensor v5.14.7803
3.0.101-108.98-default	Falcon sensor v5.14.7803
3.0.101-108.101-default	Falcon sensor v5.17.8103
3.0.101-108.108	Falcon sensor v5.20.8406
3.0.101-108.111	Falcon sensor v5.31.9606

SLES 12 SP1

Kernel	Minimum sensor version
3.12.49-11-default	Earlier than v3.4
3.12.51-60.20-default	Earlier than v3.4
3.12.51-60.25-default	Earlier than v3.4
3.12.53-60.30-default	Earlier than v3.4
3.12.57-60.35-default	Earlier than v3.4
3.12.59-60.41-default	Earlier than v3.4
3.12.59-60.45-default	Earlier than v3.4
3.12.62-60.62-default	Earlier than v3.4
3.12.62-60.64.8-default	Earlier than v3.4
3.12.67-60.64.18-default	Earlier than v3.4
3.12.67-60.64.21-default	Earlier than v3.4
3.12.67-60.64.24-default	Earlier than v3.4
3.12.69-60.64.29-default	Falcon sensor v3.4
3.12.69-60.64.32-default	Falcon sensor v3.4
3.12.69-60.64.35-default	Falcon sensor v3.4
3.12.74-60.64.40-default	Falcon sensor v3.4
3.12.74-60.64.45-default	Falcon sensor v3.7
3.12.74-60.64.48-default	Falcon sensor v3.7
3.12.74-60.64.51-default	Falcon sensor v3.7
3.12.74-60.64.54-default	Falcon sensor v3.7
3.12.74-60.64.57-default	Falcon sensor v3.7
3.12.74-60.64.60-default	Falcon sensor v3.7

3.12.74-60.64.63-default	Falcon sensor v3.10.4204
3.12.74-60.64.66-default	Falcon sensor v3.8
3.12.74-60.64.69-default	Falcon sensor v3.8
3.12.74-60.64.82-default	Falcon sensor v4.1.4404
3.12.74-60.64.88-default	Falcon sensor v4.5.5014
3.12.74-60.64.93-default	Falcon sensor v4.5.5014
3.12.74-60.64.96-default	Falcon sensor v4.10.5501
3.12.74-60.64.99-default	Falcon sensor v4.12.5704
3.12.74-60.64.104-default	Falcon sensor v4.13.5806
3.12.74-60.64.107-default	Falcon sensor v4.16.6101
3.12.74-60.64.110-default	Falcon sensor v5.10.7403
3.12.74-60.64.115-default	Falcon sensor v5.12.7602
3.12.74-60.64.118-default	Falcon sensor v5.14.7803
3.12.74-60.64.121-default	Falcon sensor v5.17.8103
3.12.74-60.64.124	Falcon sensor v5.20.8406

SLES 12 SP2

Kernel	Minimum sensor version
4.4.21-69-default	Earlier than v3.4
4.4.21-81-default	Earlier than v3.4
4.4.21-84-default	Earlier than v3.4
4.4.21-90-default	Earlier than v3.4
4.4.38-93-default	Earlier than v3.4
4.4.49-92.11-default	Earlier than v3.4
4.4.49-92.14-default	Falcon sensor v3.4
4.4.59-92.17-default	Falcon sensor v3.4
4.4.59-92.20-default	Falcon sensor v3.4
4.4.59-92.24-default	Falcon sensor v3.4
4.4.73-5-default	Falcon sensor v3.7
4.4.74-92.29-default	Falcon sensor v3.6
4.4.74-92.32-default	Falcon sensor v3.6
4.4.74-92.35-default	Falcon sensor v3.6
4.4.74-92.38-default	Falcon sensor v3.7
4.4.82-6.3-default	Falcon sensor v3.7
4.4.82-6.6-default	Falcon sensor v3.7
4.4.82-6.9-default	Falcon sensor v3.7
4.4.90-92.45-default	Falcon sensor v3.10.4204
4.4.90-92.50-default	Falcon sensor v3.8
4.4.114-92.64	Falcon sensor v4.1
4.4.121-92.73-default	Falcon sensor v4.5.5014

4.4.121-92.80-default	Falcon sensor v4.5.5014
4.4.121-92.85-default	Falcon sensor v4.11.5605
4.4.121-92.92-default	Falcon sensor v4.11.5609
4.4.121-92.95-default	Falcon sensor v4.16.6101
4.4.121-92.98-default	Falcon sensor v4.16.6106
4.4.121-92.101-default	Falcon sensor v4.22.6805
4.4.121-92.104-default	Falcon sensor v4.25.7103
4.4.121-92.109-default	Falcon sensor v5.10.7403
4.4.121-92.114-default	Falcon sensor v5.12.7602
4.4.121-92.117-default	Falcon sensor v5.14.7803
4.4.121-92.120-default	Falcon sensor v5.17.8103
4.4.121-92.125-default	Falcon sensor v5.20.8406
4.4.121-92.129-default	Falcon sensor v5.31.9607

SLES 12 SP3

Kernel	Minimum sensor version
4.4.92-6.18-default	Falcon sensor v3.8
4.4.92-6.30-default	Falcon sensor v3.8
4.4.103-6.33-default	Falcon sensor v3.8
4.4.103-6.38-default	Falcon sensor v3.8
4.4.103-92.53-default	Falcon sensor v3.8
4.4.103-92.56-default	Falcon sensor v3.8
4.4.114-94.11	Falcon sensor v4.1.4403
4.4.114-94.14-default	Falcon sensor v4.1.4404
4.4.126-94.22-default	Falcon sensor v4.5.5014
4.4.132-94.33-default	Falcon sensor v4.8.5305
4.4.138-94.39-default	Falcon sensor v4.10.5501
4.4.140-94.42-default	Falcon sensor v4.11.5605
4.4.143-94.47-default	Falcon sensor v4.11.5609
4.4.155-94.50-default	Falcon sensor v4.13.5806
4.4.156-94.57-default	Falcon sensor v4.13.5809
4.4.156-94.61-default	Falcon sensor v4.16.6101
4.4.156-94.64-default	Falcon sensor v4.16.6106
4.4.162-94.69-default	Falcon sensor v4.16.6109
4.4.162-94.72-default	Falcon sensor v4.16.6109
4.4.175-94.79-default	Falcon sensor v4.23.6903
4.4.176-94.88-default	Falcon sensor v4.25.7103
4.4.178-94.91-default	Falcon sensor v5.10.7403
4.4.180-94.97-default	Falcon sensor v5.12.7602
4.4.180-94.100-default	Falcon sensor v5.15.7901

4.4.180-94.103-default	Falcon sensor v5.17.8103
4.4.180-94.107	Falcon sensor v5.20.8406
4.4.180-94.113	Falcon sensor v5.23.8706
4.4.180-94.116-default	Falcon sensor v5.31.9607
4.18.0-147.20.1.el8_1.x86_64	Falcon sensor v5.33.9806

SLES 12 SP4

Kernel	Minimum sensor version
4.12.14-94.41-default	Falcon sensor v4.24.7002
4.12.14-95.3-default	Falcon sensor v4.24.7002
4.12.14-95.6-default	Falcon sensor v4.24.7002
4.12.14-95.13-default	Falcon sensor v4.25.7103
4.12.14-95.16-default	Falcon sensor v5.10.7403
4.12.14-95.19-default	Falcon sensor v5.12.7602
4.12.14-95.24-default	Falcon sensor v5.14.7803
4.12.14-95.29-default	Falcon sensor v5.16.8002
4.12.14-95.32-default	Falcon sensor v5.18.8202
4.12.14-95.37-default	Falcon sensor v5.20.8404
4.12.14-95.40	Falcon sensor v5.20.8406
4.12.14-95.45	Falcon sensor v5.23.8706
4.12.14-95.48	Falcon sensor v5.27.9105
4.12.14-95.51	Falcon sensor v5.31.9606
4.4.121-92.135-default	Falcon sensor v5.33.9804
4.4.180-94.121-default	Falcon sensor v5.33.9804
4.12.14-95.54-default	Falcon sensor v5.33.9804
4.12.14-197.45-default	Falcon sensor v5.33.9804

SLES 12 SP5

Kernel	Minimum sensor version
4.12.14-120	Falcon sensor v5.27.9101
4.12.14-122.7	Falcon sensor v5.27.9101
4.12.14-122.12	Falcon sensor v5.27.9101
4.12.14-122.17	Falcon sensor v5.27.9105
4.12.14-122.20-default	Falcon sensor v5.33.9806
4.12.14-122.23-default	Falcon sensor v5.33.9806
4.12.14-122.26-default	Falcon sensor v5.33.9806

SLES 15

Kernel	Minimum sensor version
4.12.14-23.1	Falcon sensor v4.26.7203
4.12.14-25.3.1	Falcon sensor v4.26.7203
4.12.14-25.6.1	Falcon sensor v4.26.7203
4.12.14-25.13.1	Falcon sensor v4.26.7203
4.12.14-25.16.1	Falcon sensor v4.26.7203
4.12.14-25.19.1	Falcon sensor v4.26.7203
4.12.14-25.22.1	Falcon sensor v4.26.7203
4.12.14-25.25.1	Falcon sensor v4.26.7203
4.12.14-25.28.1	Falcon sensor v4.26.7203
4.12.14-150.14.2	Falcon sensor v4.26.7203
4.12.14-150.17-default	Falcon sensor v5.10.7403
4.12.14-150.22-default	Falcon sensor v5.12.7602
4.12.14-150.27-default	Falcon sensor v5.14.7803
4.12.14-150.32-default	Falcon sensor v5.16.8002
4.12.14-197.15-default	Falcon sensor v5.16.8002
4.12.14-150.35-default	Falcon sensor v5.18.8202
4.12.14-150.38	Falcon sensor v5.20.8402
4.12.14-150.41	Falcon sensor v5.20.8406
4.12.14-150.47	Falcon sensor v5.23.8706

SLES 15 SP1

Kernel	Minimum sensor version
4.12.14-195-default	Falcon sensor v5.15.7901
4.12.14-197.4-default	Falcon sensor v5.15.7901
4.12.14-197.7-default	Falcon sensor v5.15.7901
4.12.14-197.10-default	Falcon sensor v5.15.7901
4.12.14-197.18-default	Falcon sensor v5.18.8202
4.12.14-197.21	Falcon sensor v5.20.8402
4.12.14-197.26	Falcon sensor v5.20.8406
4.12.14-197.29	Falcon sensor v5.23.8705
4.12.14-197.34	Falcon sensor v5.27.9105
4.12.14-197.37	Falcon sensor v5.30.9507
4.12.14-197.40	Falcon sensor v5.31.9606
4.12.14-197.48-default	Falcon sensor v5.34.9917

Ubuntu 14.04LTS

We support these [Ubuntu LTS](#) kernels, which generally have support for at least 9-12 months.

Kernel	Minimum sensor version
--------	------------------------

3.13.0-24-generic	Falcon sensor v3.6
3.13.0-27-generic	Falcon sensor v3.6
3.13.0-29-generic	Falcon sensor v3.6
3.13.0-30-generic	Falcon sensor v3.6
3.13.0-32-generic	Falcon sensor v3.6
3.13.0-33-generic	Falcon sensor v3.6
3.13.0-34-generic	Falcon sensor v3.6
3.13.0-35-generic	Falcon sensor v3.6
3.13.0-36-generic	Falcon sensor v3.6
3.13.0-37-generic	Falcon sensor v3.6
3.13.0-39-generic	Falcon sensor v3.6
3.13.0-40-generic	Falcon sensor v3.6
3.13.0-41-generic	Falcon sensor v3.6
3.13.0-43-generic	Falcon sensor v3.6
3.13.0-44-generic	Falcon sensor v3.6
3.13.0-45-generic	Falcon sensor v3.6
3.13.0-46-generic	Falcon sensor v3.6
3.13.0-48-generic	Falcon sensor v3.6
3.13.0-49-generic	Falcon sensor v3.6
3.13.0-51-generic	Falcon sensor v3.6
3.13.0-52-generic	Falcon sensor v3.6
3.13.0-53-generic	Falcon sensor v3.6
3.13.0-54-generic	Falcon sensor v3.6
3.13.0-55-generic	Falcon sensor v3.6
3.13.0-57-generic	Falcon sensor v3.6
3.13.0-58-generic	Falcon sensor v3.6
3.13.0-59-generic	Falcon sensor v3.6
3.13.0-61-generic	Falcon sensor v3.6
3.13.0-62-generic	Falcon sensor v3.6
3.13.0-63-generic	Falcon sensor v3.6
3.13.0-65-generic	Falcon sensor v3.6
3.13.0-66-generic	Falcon sensor v3.6
3.13.0-67-generic	Falcon sensor v3.6
3.13.0-68-generic	Falcon sensor v3.6
3.13.0-70-generic	Falcon sensor v3.6
3.13.0-71-generic	Falcon sensor v3.6
3.13.0-73-generic	Falcon sensor v3.6
3.13.0-74-generic	Falcon sensor v3.6
3.13.0-76-generic	Falcon sensor v3.6
3.13.0-77-generic	Falcon sensor v3.6
3.13.0-79-generic	Falcon sensor v3.6

3.13.0-83-generic	Falcon sensor v3.6
3.13.0-85-generic	Falcon sensor v3.6
3.13.0-86-generic	Falcon sensor v3.6
3.13.0-87-generic	Falcon sensor v3.6
3.13.0-88-generic	Falcon sensor v3.6
3.13.0-91-generic	Falcon sensor v3.6
3.13.0-92-generic	Falcon sensor v3.6
3.13.0-93-generic	Falcon sensor v3.6
3.13.0-95-generic	Falcon sensor v3.6
3.13.0-96-generic	Falcon sensor v3.6
3.13.0-98-generic	Falcon sensor v3.6
3.13.0-100-generic	Falcon sensor v3.6
3.13.0-101-generic	Falcon sensor v3.6
3.13.0-103-generic	Falcon sensor v3.6
3.13.0-105-generic	Falcon sensor v3.6
3.13.0-106-generic	Falcon sensor v3.6
3.13.0-107-generic	Falcon sensor v3.6
3.13.0-108-generic	Falcon sensor v3.6
3.13.0-109-generic	Falcon sensor v3.6
3.13.0-110-generic	Falcon sensor v3.6
3.13.0-112-generic	Falcon sensor v3.6
3.13.0-113-generic	Falcon sensor v3.6
3.13.0-115-generic	Falcon sensor v3.6
3.13.0-116-generic	Falcon sensor v3.6
3.13.0-117-generic	Falcon sensor v3.6
3.13.0-119-generic	Falcon sensor v3.6
3.13.0-121-generic	Falcon sensor v3.6
3.13.0-123-generic	Falcon sensor v3.6
3.13.0-125-generic	Falcon sensor v3.6
3.13.0-126-generic	Falcon sensor v3.6
3.13.0-128-generic	Falcon sensor v3.6
3.13.0-129-generic	Falcon sensor v3.6
3.13.0-132-generic	Falcon sensor v3.7
3.13.0-133-generic	Falcon sensor v3.10.4204
3.13.0-135-generic	Falcon sensor v3.10.4204
3.13.0-137-generic	Falcon sensor v3.8
3.13.0-139-generic	Falcon sensor v3.8
3.13.0-141-generic	Falcon sensor v3.10.4205
3.13.0-142-generic	Falcon sensor v4.1.4404
4.4.0-21-generic	Falcon sensor v3.6
4.4.0-22-generic	Falcon sensor v3.6

4.4.0-24-generic	Falcon sensor v3.6
4.4.0-28-generic	Falcon sensor v3.6
4.4.0-31-generic	Falcon sensor v3.6
4.4.0-34-generic	Falcon sensor v3.6
4.4.0-36-generic	Falcon sensor v3.6
4.4.0-38-generic	Falcon sensor v3.6
4.4.0-42-generic	Falcon sensor v3.6
4.4.0-45-generic	Falcon sensor v3.6
4.4.0-47-generic	Falcon sensor v3.6
4.4.0-51-generic	Falcon sensor v3.6
4.4.0-53-generic	Falcon sensor v3.6
4.4.0-57-generic	Falcon sensor v3.6
4.4.0-59-generic	Falcon sensor v3.6
4.4.0-62-generic	Falcon sensor v3.6
4.4.0-63-generic	Falcon sensor v3.6
4.4.0-64-generic	Falcon sensor v3.6
4.4.0-66-generic	Falcon sensor v3.6
4.4.0-67-generic	Falcon sensor v3.6
4.4.0-70-generic	Falcon sensor v3.6
4.4.0-71-generic	Falcon sensor v3.6
4.4.0-72-generic	Falcon sensor v3.6
4.4.0-75-generic	Falcon sensor v3.6
4.4.0-78-generic	Falcon sensor v3.6
4.4.0-79-generic	Falcon sensor v3.6
4.4.0-81-generic	Falcon sensor v3.6
4.4.0-83-generic	Falcon sensor v3.6
4.4.0-87-generic	Falcon sensor v3.6
4.4.0-89-generic	Falcon sensor v3.6
4.4.0-91-generic	Falcon sensor v3.6
4.4.0-92-generic	Falcon sensor v3.6
4.4.0-93-generic	Falcon sensor v3.6
4.4.0-96-generic	Falcon sensor v3.7
4.4.0-97-generic	Falcon sensor v3.10.4204
4.4.0-98-generic	Falcon sensor v3.10.4204
4.4.0-101-generic	Falcon sensor v3.10.4204
4.4.0-103-generic	Falcon sensor v3.8
4.4.0-104-generic	Falcon sensor v3.8
4.4.0-108-generic	Falcon sensor v3.8
4.4.0-109-generic	Falcon sensor v3.8
4.4.0-111-generic	Falcon sensor v3.10.4205
4.4.0-112-generic	Falcon sensor v3.10.4205

3.13.0-143-generic	Falcon sensor v4.3.4603
4.4.0-116-generic	Falcon sensor v4.3.4603
3.13.0-145-generic	Falcon sensor v4.5.5011
4.4.0-121-generic	Falcon sensor v4.5.5011
3.13.0-147-generic	Falcon sensor v4.5.5014
3.13.0-149-generic	Falcon sensor v4.5.5014
4.4.0-124-generic	Falcon sensor v4.5.5014
4.4.0-127-generic	Falcon sensor v4.5.5014
3.13.0-151-generic	Falcon sensor v4.10.5501
3.13.0-153-generic	Falcon sensor v4.11.5605
4.4.0-130-generic	Falcon sensor v4.11.5605
4.4.0-131-generic	Falcon sensor v4.11.5605
3.13.0-155-generic	Falcon sensor v4.11.5609
4.4.0-133-generic	Falcon sensor v4.11.5609
4.4.0-128-generic	Falcon sensor v4.10.5501
3.13.0-156-generic	Falcon sensor v4.12.5704
3.13.0-157-generic	Falcon sensor v4.13.5803
3.13.0-158-generic	Falcon sensor v4.13.5803
4.4.0-134-generic	Falcon sensor v4.13.5803
4.4.0-135-generic	Falcon sensor v4.13.5803
3.13.0-160-generic	Falcon sensor v4.13.5806
4.4.0-137-generic	Falcon sensor v4.13.5806
3.13.0-161-generic	Falcon sensor v4.16.6106
4.4.0-138-generic	Falcon sensor v4.16.6106
3.13.0-162-generic	Falcon sensor v4.16.6109
4.4.0-139-generic	Falcon sensor v4.16.6109
3.13.0-163-generic	Falcon sensor v4.18.6402
4.4.0-140-generic	Falcon sensor v4.18.6402
3.13.0-164-generic	Falcon sensor v4.18.6403
4.4.0-141-generic	Falcon sensor v4.18.6403
3.13.0-165-generic	Falcon sensor v4.21.6705
4.4.0-142-generic	Falcon sensor v4.21.6705
3.13.0-166-generic	Falcon sensor v4.24.7002
3.13.0-167-generic	Falcon sensor v4.24.7002
4.4.0-143-generic	Falcon sensor v4.24.7002
3.13.0-168-generic	Falcon sensor v4.26.7203
4.4.0-144-generic	Falcon sensor v4.26.7203
3.13.0-169-generic	Falcon sensor v4.28.7303
4.4.0-146-generic	Falcon sensor v4.28.7303
3.13.0-170-generic	Falcon sensor v5.10.7403
4.4.0-148-generic	Falcon sensor v5.10.7403

4.15.0-60-generic	Falcon sensor v5.17.8103
4.4.0-161-generic	Falcon sensor v5.17.8103
4.4.0-1092-aws	Falcon sensor v5.17.8103

Ubuntu 16.04LTS

We support these [Ubuntu LTS](#) kernels, which generally have support for at least 9-12 months.

Kernel	Minimum sensor version
4.4.0-21-generic	Falcon sensor v3.6
4.4.0-22-generic	Falcon sensor v3.6
4.4.0-24-generic	Falcon sensor v3.6
4.4.0-28-generic	Falcon sensor v3.6
4.4.0-31-generic	Falcon sensor v3.6
4.4.0-34-generic	Falcon sensor v3.6
4.4.0-36-generic	Falcon sensor v3.6
4.4.0-38-generic	Falcon sensor v3.6
4.4.0-42-generic	Falcon sensor v3.6
4.4.0-43-generic	Falcon sensor v3.6
4.4.0-45-generic	Falcon sensor v3.6
4.4.0-47-generic	Falcon sensor v3.6
4.4.0-51-generic	Falcon sensor v3.6
4.4.0-53-generic	Falcon sensor v3.6
4.4.0-57-generic	Falcon sensor v3.6
4.4.0-59-generic	Falcon sensor v3.6
4.4.0-62-generic	Falcon sensor v3.6
4.4.0-63-generic	Falcon sensor v3.6
4.4.0-64-generic	Falcon sensor v3.6
4.4.0-66-generic	Falcon sensor v3.6
4.4.0-67-generic	Falcon sensor v3.6
4.4.0-70-generic	Falcon sensor v3.6
4.4.0-71-generic	Falcon sensor v3.6
4.4.0-72-generic	Falcon sensor v3.6
4.4.0-75-generic	Falcon sensor v3.6
4.4.0-77-generic	Falcon sensor v3.6
4.4.0-78-generic	Falcon sensor v3.6
4.4.0-79-generic	Falcon sensor v3.6
4.4.0-81-generic	Falcon sensor v3.6
4.4.0-83-generic	Falcon sensor v3.6
4.4.0-87-generic	Falcon sensor v3.6
4.4.0-89-generic	Falcon sensor v3.6
4.4.0-91-generic	Falcon sensor v3.6

4.4.0-92-generic	Falcon sensor v3.6
4.4.0-93-generic	Falcon sensor v3.6
4.4.0-96-generic	Falcon sensor v3.7
4.4.0-97-generic	Falcon sensor v3.10.4204
4.4.0-98-generic	Falcon sensor v3.10.4204
4.4.0-101-generic	Falcon sensor v3.10.4204
4.4.0-103-generic	Falcon sensor v3.8
4.4.0-104-generic	Falcon sensor v3.8
4.4.0-108-generic	Falcon sensor v3.8
4.4.0-109-generic	Falcon sensor v3.8
4.4.0-112-generic	Falcon sensor v3.10.4205
4.4.0-116-generic	Falcon sensor v4.5.5015
4.4.0-119-generic	Falcon sensor v4.5.5015
4.4.0-121-generic	Falcon sensor v4.5.5015
4.4.0-122-generic	Falcon sensor v4.5.5015
4.4.0-124-generic	Falcon sensor v4.5.5015
4.4.0-127-generic	Falcon sensor v4.5.5015
4.4.0-128-generic	Falcon sensor v4.10.5501
4.4.0-130-generic	Falcon sensor v4.11.5605
4.4.0-131-generic	Falcon sensor v4.11.5605
4.4.0-133-generic	Falcon sensor v4.11.5609
4.4.0-134-generic	Falcon sensor v4.13.5803
4.4.0-135-generic	Falcon sensor v4.13.5803
4.4.0-137-generic	Falcon sensor v4.13.5806
4.4.0-1001-aws	Falcon sensor v3.7
4.4.0-1003-aws	Falcon sensor v3.7
4.4.0-1004-aws	Falcon sensor v3.7
4.4.0-1007-aws	Falcon sensor v3.7
4.4.0-1009-aws	Falcon sensor v3.7
4.4.0-1011-aws	Falcon sensor v3.7
4.4.0-1012-aws	Falcon sensor v3.7
4.4.0-1013-aws	Falcon sensor v3.7
4.4.0-1016-aws	Falcon sensor v3.7
4.4.0-1017-aws	Falcon sensor v3.7
4.4.0-1018-aws	Falcon sensor v3.7
4.4.0-1020-aws	Falcon sensor v3.7
4.4.0-1022-aws	Falcon sensor v3.7
4.4.0-1026-aws	Falcon sensor v3.7
4.4.0-1028-aws	Falcon sensor v3.7
4.4.0-1030-aws	Falcon sensor v3.7
4.4.0-1031-aws	Falcon sensor v3.7

4.4.0-1032-aws	Falcon sensor v3.7
4.4.0-1035-aws	Falcon sensor v3.7
4.4.0-1037-aws	Falcon sensor v3.7
4.4.0-1038-aws	Falcon sensor v3.10.4204
4.4.0-1039-aws	Falcon sensor v3.10.4204
4.4.0-1041-aws	Falcon sensor v3.10.4204
4.4.0-1043-aws	Falcon sensor v3.8
4.4.0-1044-aws	Falcon sensor v3.8
4.4.0-1047-aws	Falcon sensor v3.8
4.4.0-1048-aws	Falcon sensor v3.8
4.4.0-1049-aws	Falcon sensor v3.10.4205
4.4.0-1050-aws	Falcon sensor v4.1.4404
4.4.0-1052-aws	Falcon sensor v4.5.5015
4.4.0-1054-aws	Falcon sensor v4.5.5015
4.4.0-1055-aws	Falcon sensor v4.5.5015
4.4.0-1057-aws	Falcon sensor v4.5.5015
4.4.0-1060-aws	Falcon sensor v4.5.5015
4.4.0-1061-aws	Falcon sensor v4.10.5501
4.4.0-130-aws	Falcon sensor v4.11.5605
4.4.0-131-aws	Falcon sensor v4.11.5605
4.4.0-1065-aws	Falcon sensor v4.11.5609
4.4.0-1066-aws	Falcon sensor v4.13.5803
4.4.0-1067-aws	Falcon sensor v4.13.5803
4.4.0-1069-aws	Falcon sensor v4.13.5806
4.4.0-138-generic	Falcon sensor v4.16.6106
4.4.0-1070-aws	Falcon sensor v4.16.6106
4.15.0-38-generic	Falcon sensor v4.16.6106
4.4.0-139-generic	Falcon sensor v4.16.6109
4.4.0-1072-aws	Falcon sensor v4.16.6109
4.15.0-39-generic	Falcon sensor v4.16.6109
4.15.0-1027-aws	Falcon sensor v4.16.6109
4.4.0-140-generic	Falcon sensor v4.18.6402
4.4.0-1073-aws	Falcon sensor v4.18.6402
4.15.0-42-generic	Falcon sensor v4.18.6402
4.4.0-141-generic	Falcon sensor v4.18.6403
4.4.0-1074-aws	Falcon sensor v4.18.6403
4.15.0-43-generic	Falcon sensor v4.18.6403
4.4.0-142-generic	Falcon sensor v4.21.6705
4.15.0-45-generic	Falcon sensor v4.21.6705
4.4.0-1075-aws	Falcon sensor v4.21.6705
4.15.0-46-generic	Falcon sensor v4.24.7002

4.4.0-143-generic	Falcon sensor v4.24.7002
4.4.0-1077-aws	Falcon sensor v4.24.7002
4.15.0-47-generic	Falcon sensor v4.26.7203
4.4.0-145-generic	Falcon sensor v4.26.7203
4.4.0-1079-aws	Falcon sensor v4.26.7203
4.4.0-146-generic	Falcon sensor v4.28.7303
4.15.0-48-generic	Falcon sensor v4.28.7303
4.4.0-1081-aws	Falcon sensor v4.28.7303
4.4.0-148-generic	Falcon sensor v5.10.7403
4.15.0-50-generic	Falcon sensor v5.10.7403
4.4.0-1083-aws	Falcon sensor v5.10.7403
4.4.0-150-generic	Falcon sensor v5.12.7602
4.4.0-151-generic	Falcon sensor v5.12.7602
4.15.0-52-generic	Falcon sensor v5.12.7602
4.15.0-51-generic	Falcon sensor v5.12.7602
4.4.0-1084-aws	Falcon sensor v5.12.7602
4.4.0-1085-aws	Falcon sensor v5.12.7602
4.4.0-154-generic	Falcon sensor v5.12.7603
4.4.0-1087-aws	Falcon sensor v5.12.7603
4.15.0-54-generic	Falcon sensor v5.12.7603
4.4.0-157-generic	Falcon sensor v5.15.7901
4.4.0-1088-aws	Falcon sensor v5.15.7901
4.15.0-55-generic	Falcon sensor v5.15.7901
4.4.0-159-generic	Falcon sensor v5.17.8101
4.4.0-1090-aws	Falcon sensor v5.17.8101
4.15.0-58-generic	Falcon sensor v5.17.8101
4.15.0-62-generic	Falcon sensor v5.18.8201
4.4.0-164-generic	Falcon sensor v5.18.8202
4.4.0-1094-aws	Falcon sensor v5.18.8202
4.15.0-64-generic	Falcon sensor v5.18.8202
4.4.0-165-generic	Falcon sensor v5.18.8203
4.4.0-1095-aws	Falcon sensor v5.18.8203
4.15.0-65-generic	Falcon sensor v5.18.8203
4.15.0-1014-gcp	Falcon sensor v5.20.8402
4.15.0-1015-gcp	Falcon sensor v5.20.8402
4.15.0-1017-gcp	Falcon sensor v5.20.8402
4.15.0-1018-gcp	Falcon sensor v5.20.8402
4.15.0-1019-gcp	Falcon sensor v5.20.8402
4.15.0-1021-gcp	Falcon sensor v5.20.8402
4.15.0-1023-gcp	Falcon sensor v5.20.8402
4.15.0-1024-gcp	Falcon sensor v5.20.8402

4.15.0-1025-gcp	Falcon sensor v5.20.8402
4.15.0-1026-gcp	Falcon sensor v5.20.8402
4.15.0-1027-gcp	Falcon sensor v5.20.8402
4.15.0-1028-gcp	Falcon sensor v5.20.8402
4.15.0-1029-gcp	Falcon sensor v5.20.8402
4.15.0-1030-gcp	Falcon sensor v5.20.8402
4.15.0-1032-gcp	Falcon sensor v5.20.8402
4.15.0-1033-gcp	Falcon sensor v5.20.8402
4.15.0-1034-gcp	Falcon sensor v5.20.8402
4.15.0-1036-gcp	Falcon sensor v5.20.8402
4.15.0-1037-gcp	Falcon sensor v5.20.8402
4.15.0-1040-gcp	Falcon sensor v5.20.8402
4.15.0-1041-gcp	Falcon sensor v5.20.8402
4.15.0-1042-gcp	Falcon sensor v5.20.8402
4.15.0-1044-gcp	Falcon sensor v5.20.8402
4.15.0-1046-gcp	Falcon sensor v5.20.8402
4.4.0-166-generic	Falcon sensor v5.20.8404
4.4.0-1096-aws	Falcon sensor v5.20.8404
4.15.0-66-generic	Falcon sensor v5.20.8404
4.15.0-1047-gcp	Falcon sensor v5.20.8404
4.15.0-69-generic	Falcon sensor v5.20.8406
4.4.0-168-generic	Falcon sensor v5.20.8406
4.4.0-169-generic	Falcon sensor v5.20.8406
4.4.0-1098-aws	Falcon sensor v5.20.8406
4.4.0-170-generic	Falcon sensor v5.23.8703
4.4.0-1099-aws	Falcon sensor v5.23.8703
4.15.0-72-generic	Falcon sensor v5.23.8703
4.15.0-1050-gcp	Falcon sensor v5.23.8703
4.4.0-171	Falcon sensor v5.23.8706
4.15.0-74	Falcon sensor v5.23.8706
4.4.0-1100-aws	Falcon sensor v5.23.8706
4.15.0-1052-gcp	Falcon sensor v5.23.8706
4.4.0-173-generic	Falcon sensor v5.26.9003
4.4.0-1101-aws	Falcon sensor v5.26.9003
4.15.0-76-generic	Falcon sensor v5.26.9003
4.4.0-1102-aws	Falcon sensor v5.27.9104
4.15.0-1055-gcp	Falcon sensor v5.27.9104
4.4.0-174-generic	Falcon sensor v5.27.9104
4.15.0-88-generic	Falcon sensor v5.27.9104
4.4.0-176-generic	Falcon sensor v5.29.9402
4.4.0-1104-aws	Falcon sensor v5.29.9402

4.15.0-91-generic	Falcon sensor v5.29.9402
4.15.0-1058-gcp	Falcon sensor v5.29.9402
4.4.0-177-generic	Falcon sensor v5.30.9507
4.4.0-1105-aws	Falcon sensor v5.30.9507
4.15.0-96-generic	Falcon sensor v5.30.9507
4.15.0-1060-gcp	Falcon sensor v5.30.9507
4.4.0-1106-aws	Falcon sensor v5.31.9606
4.4.0-178-generic	Falcon sensor v5.31.9606
4.15.0-1061-gcp	Falcon sensor v5.31.9606
4.15.0-99-generic	Falcon sensor v5.31.9606
4.4.0-179-generic	Falcon sensor v5.31.9607
4.4.0-1107-aws	Falcon sensor v5.31.9607
4.15.0-101-generic	Falcon sensor v5.31.9607
4.15.0-1071-gcp	Falcon sensor v5.31.9607
4.4.0-184-generic	Falcon sensor v5.33.9804
4.4.0-1109-aws	Falcon sensor v5.33.9804
4.15.0-106-generic	Falcon sensor v5.33.9804
4.15.0-1071-gcp	Falcon sensor v5.33.9804
4.15.0-1077-gcp	Falcon sensor v5.33.9804
4.15.0-1080-gcp	Falcon sensor v5.34.9917
4.15.0-112-generic	Falcon sensor v5.34.9917
4.4.0-1111-aws	Falcon sensor v5.34.9917
4.4.0-186-generic	Falcon sensor v5.34.9917

Ubuntu 16.04.5

Kernel	Minimum sensor version
4.15.0-13-generic	Falcon sensor v4.15.6003
4.15.0-15-generic	Falcon sensor v4.15.6003
4.15.0-20-generic	Falcon sensor v4.15.6003
4.15.0-22-generic	Falcon sensor v4.15.6003
4.15.0-23-generic	Falcon sensor v4.15.6003
4.15.0-24-generic	Falcon sensor v4.15.6003
4.15.0-29-generic	Falcon sensor v4.15.6003
4.15.0-30-generic	Falcon sensor v4.15.6003
4.15.0-32-generic	Falcon sensor v4.15.6003
4.15.0-33-generic	Falcon sensor v4.15.6003
4.15.0-34-generic	Falcon sensor v4.15.6003
4.15.0-36-generic	Falcon sensor v4.15.6003

Ubuntu 18.04 LTS

Kernel	Minimum sensor version
4.15.0-20-generic	Falcon sensor v4.16.6106
4.15.0-22-generic	Falcon sensor v4.16.6106
4.15.0-23-generic	Falcon sensor v4.16.6106
4.15.0-24-generic	Falcon sensor v4.16.6106
4.15.0-29-generic	Falcon sensor v4.16.6106
4.15.0-30-generic	Falcon sensor v4.16.6106
4.15.0-32-generic	Falcon sensor v4.16.6106
4.15.0-33-generic	Falcon sensor v4.16.6106
4.15.0-34-generic	Falcon sensor v4.16.6106
4.15.0-36-generic	Falcon sensor v4.16.6106
4.15.0-38-generic	Falcon sensor v4.16.6106
4.15.0-1007-aws	Falcon sensor v4.16.6106
4.15.0-1009-aws	Falcon sensor v4.16.6106
4.15.0-1010-aws	Falcon sensor v4.16.6106
4.15.0-1011-aws	Falcon sensor v4.16.6106
4.15.0-1016-aws	Falcon sensor v4.16.6106
4.15.0-1017-aws	Falcon sensor v4.16.6106
4.15.0-1019-aws	Falcon sensor v4.16.6106
4.15.0-1020-aws	Falcon sensor v4.16.6106
4.15.0-1021-aws	Falcon sensor v4.16.6106
4.15.0-1023-aws	Falcon sensor v4.16.6106
4.15.0-1025-aws	Falcon sensor v4.16.6106
4.15.0-39-generic	Falcon sensor v4.16.6109
4.15.0-42-generic	Falcon sensor v4.18.6402
4.15.0-1029-aws	Falcon sensor v4.18.6402
4.15.0-43-generic	Falcon sensor v4.18.6403
4.15.0-1031-aws	Falcon sensor v4.18.6403
4.15.0-44-generic	Falcon sensor v4.21.6705
4.15.0-45-generic	Falcon sensor v4.21.6705
4.15.0-1032-aws	Falcon sensor v4.21.6705
4.15.0-46-generic	Falcon sensor v4.24.7002
4.15.0-1033-aws	Falcon sensor v4.24.7002
4.15.0-1034-aws	Falcon sensor v4.24.7002
4.15.0-47-generic	Falcon sensor v4.26.7203
4.15.0-1035-aws	Falcon sensor v4.26.7203
4.15.0-48-generic	Falcon sensor v4.28.7303
4.15.0-1037-aws	Falcon sensor v4.28.7303
4.15.0-50-generic	Falcon sensor v5.10.7403
4.15.0-1039-aws	Falcon sensor v5.10.7403
4.15.0-51-generic	Falcon sensor v5.12.7602

4.15.0-52-generic	Falcon sensor v5.12.7602
4.15.0-1040-aws	Falcon sensor v5.12.7602
4.15.0-1041-aws	Falcon sensor v5.12.7602
4.15.0-54-generic	Falcon sensor v5.12.7603
4.15.0-1043-aws	Falcon sensor v5.12.7603
4.15.0-55-generic	Falcon sensor v5.15.7901
4.15.0-1044-aws	Falcon sensor v5.15.7901
4.15.0-1045-aws	Falcon sensor v5.16.8002
4.15.0-58-generic	Falcon sensor v5.17.8101
4.15.0-60-generic	Falcon sensor v5.17.8103
4.15.0-1047-aws	Falcon sensor v5.17.8103
4.15.0-62-generic	Falcon sensor v5.18.8201
4.15.0-1048-aws	Falcon sensor v5.18.8201
4.15.0-64-generic	Falcon sensor v5.18.8202
4.15.0-1050-aws	Falcon sensor v5.18.8202
4.15.0-65-generic	Falcon sensor v5.18.8203
4.15.0-1051-aws	Falcon sensor v5.18.8203
4.15.0-1006-gcp	Falcon sensor v5.20.8402
4.15.0-1008-gcp	Falcon sensor v5.20.8402
4.15.0-1009-gcp	Falcon sensor v5.20.8402
4.15.0-1014-gcp	Falcon sensor v5.20.8402
4.15.0-1015-gcp	Falcon sensor v5.20.8402
4.15.0-1017-gcp	Falcon sensor v5.20.8402
4.15.0-1018-gcp	Falcon sensor v5.20.8402
4.15.0-1019-gcp	Falcon sensor v5.20.8402
4.15.0-1021-gcp	Falcon sensor v5.20.8402
4.15.0-1023-gcp	Falcon sensor v5.20.8402
4.15.0-1024-gcp	Falcon sensor v5.20.8402
4.15.0-1025-gcp	Falcon sensor v5.20.8402
4.15.0-1026-gcp	Falcon sensor v5.20.8402
4.15.0-1027-gcp	Falcon sensor v5.20.8402
4.15.0-1028-gcp	Falcon sensor v5.20.8402
4.15.0-1029-gcp	Falcon sensor v5.20.8402
4.15.0-1030-gcp	Falcon sensor v5.20.8402
4.15.0-1032-gcp	Falcon sensor v5.20.8402
4.15.0-1033-gcp	Falcon sensor v5.20.8402
4.15.0-1034-gcp	Falcon sensor v5.20.8402
4.15.0-1036-gcp	Falcon sensor v5.20.8402
4.15.0-1037-gcp	Falcon sensor v5.20.8402
4.15.0-1040-gcp	Falcon sensor v5.20.8402
4.15.0-1042-gcp	Falcon sensor v5.20.8402

4.15.0-1044-gcp	Falcon sensor v5.20.8402
4.15.0-66-generic	Falcon sensor v5.20.8404
4.15.0-1052-aws	Falcon sensor v5.20.8404
4.15.0-69-generic	Falcon sensor v5.20.8406
4.15.0-70-generic	Falcon sensor v5.20.8406
4.15.0-1054-aws	Falcon sensor v5.20.8406
4.15.0-72-generic	Falcon sensor v5.23.8703
4.15.0-1056-aws	Falcon sensor v5.23.8703
4.15.0-74	Falcon sensor v5.23.8706
4.15.0-1057-aws	Falcon sensor v5.23.8706
4.15.0-76-generic	Falcon sensor v5.26.9003
4.15.0-1058-aws	Falcon sensor v5.26.9003
5.0.0-1011-gcp	Falcon sensor v5.27.9101
5.0.0-1013-gcp	Falcon sensor v5.27.9101
5.0.0-1020-gcp	Falcon sensor v5.27.9101
5.0.0-1021-gcp	Falcon sensor v5.27.9101
5.0.0-1025-gcp	Falcon sensor v5.27.9101
5.0.0-1026-gcp	Falcon sensor v5.27.9101
5.0.0-1028-gcp	Falcon sensor v5.27.9101
5.0.0-1029-gcp	Falcon sensor v5.27.9101
4.15.0-88-generic	Falcon sensor v5.27.9104
4.15.0-1060-aws	Falcon sensor v5.28.9205
5.0.0-1031-gcp	Falcon sensor v5.28.9205
4.15.0-91-generic	Falcon sensor v5.29.9402
4.15.0-1063-aws	Falcon sensor v5.29.9402
5.0.0-1033-gcp	Falcon sensor v5.29.9402
4.15.0-96-generic	Falcon sensor v5.30.9507
4.15.0-1065-aws	Falcon sensor v5.30.9507
4.15.0-1066-aws	Falcon sensor v5.31.9606
4.15.0-99-generic	Falcon sensor v5.31.9606
4.15.0-101-generic	Falcon sensor v5.31.9607
4.15.0-1067-aws	Falcon sensor v5.31.9607
4.15.0-1010-gcp	Falcon sensor v5.32.9704
4.15.0-106-generic	Falcon sensor v5.33.9804
4.15.0-1071-gcp	Falcon sensor v5.33.9804
4.15.0-1073-aws	Falcon sensor v5.33.9804
4.15.0-1077-gcp	Falcon sensor v5.33.9804
4.15.0-1079-aws	Falcon sensor v5.34.9917
4.15.0-1080-gcp	Falcon sensor v5.34.9917
4.15.0-112-generic	Falcon sensor v5.34.9917
5.3.0-1016-aws	Falcon sensor v5.34.9917

5.3.0-1017-aws	Falcon sensor v5.34.9917
5.3.0-1019-aws	Falcon sensor v5.34.9917
5.3.0-1023-aws	Falcon sensor v5.34.9917
5.3.0-1028-aws	Falcon sensor v5.34.9917
5.3.0-1030-aws	Falcon sensor v5.34.9917
5.3.0-1032-aws	Falcon sensor v5.34.9917